# Programming in GILDAS

a GILDAS working group software

March 12, 1999

**GILDAS**
**Programming Guide**
Version 1.0

The GILDAS working group is a collaborative project of the Observatoire de Grenoble (1,3) and IRAM (2), and comprises: F. Badia[2], D. Broguière[2], G. Buisson[1], L. Desbats[1], G. Duvert[1], T. Forveille[1], R.Gras[3], S. Guilloteau[1,2], R. Lucas[1,2], R. Neri[2] and P. Valiron[1].

(1) Laboratoire d'Astrophysique
Observatoire de Grenoble
BP 53 X
414 Rue de la Piscine
F-38402 Saint Martin d'Hères CEDEX

(2) Institut de Radio Astronomie Millimétrique
300 Rue de la Piscine
F-38406 Saint Martin d'Hères

(3) CEPHAG
Observatoire de Grenoble
F-38402 Saint Martin d'Hères CEDEX

Contributions from and invaluable discussions with J. Cernicharo, P. Begou[3], S. Delahaye[3], A. Dutrey[1,2], C. Kahane[1], P. Monger, J.L. Monin[1] and all **GILDAS** users are gratefully acknowledged.

# Contents

**1 Introduction** **4**

**2 SIC Programming Manual** **5**
2.1 Introduction . . . 5
2.2 Initializing SIC: The Command Language Structure . . . 6
2.3 The Program Structure . . . 7
2.4 The Help File . . . 11
2.5 Retrieving Arguments . . . 11
2.6 The Library Version . . . 12
2.6.1 Creating the Library Interface . . . 12
2.6.2 Library Only Mode . . . 13
2.6.3 Reserved logical unit numbers: VMS . . . 14
2.6.4 Reserved logical unit numbers: UNIX . . . 14
2.6.5 Linking on VMS . . . 14
2.6.6 Linking on UNIX . . . 15
2.7 Using Variables . . . 15
2.7.1 Definition . . . 15
2.7.2 Assignment and Examination . . . 16
2.7.3 Mathematical Formula Handling . . . 17
2.7.4 Deleting Variables . . . 17
2.8 Using Functions . . . 18
2.9 SIC Callable Routines . . . 18
2.9.1 Monitor interface routines . . . 18
2.9.2 SIC Arguments Retrieving Routines . . . 21
2.9.3 Command Line Interpretor Subroutines . . . 22
2.9.4 All Purpose General Subroutines . . . 23
2.9.5 Symbol Manipulation Routines . . . 23

**3 GreG Programming Manual** **24**
3.1 Interaction with FORTRAN programs . . . 24
3.2 Basic Routines . . . 25
3.3 Linking . . . 26
3.3.1 UNIX systems . . . 26
3.3.2 VMS systems . . . 26
3.4 Running . . . 27
3.5 Example . . . 27
3.6 Array Transfer . . . 27
3.6.1 GR4_GIVE - GR8_GIVE . . . 27
3.6.2 GR4_GET - GR8_GET . . . 27
3.6.3 GR4_RGIVE - GR8_RGIVE . . . 27
3.6.4 GR4_LEVELS - GR8_LEVELS . . . 28
3.7 Immediate Routines . . . 28
3.7.1 GR_SEGM . . . 28
3.7.2 GR_OUT . . . 28
3.7.3 DRAW - RELOCATE . . . 28
3.7.4 GDRAW - GRELOCATE . . . 28
3.7.5 GR4_PHYS_USER - GR8_PHYS_USER . . . 29
3.7.6 GR4_USER_PHYS - GR8_USER_PHYS . . . 29
3.7.7 GR4_CONNECT - GR8_CONNECT . . . 29
3.7.8 GR4_HISTO - GR8_HISTO . . . 29
3.7.9 GR4_MARKER - GR8_MARKER . . . 29
3.7.10 GR4_CURVE - GR8_CURVE . . . 29

3.7.11 GR4_EXTREMA - GR8_EXTREMA . . . 30
3.7.12 GR8_BLANKING . . . 30
3.7.13 GR8_SYSTEM - GR8_PROJEC . . . 30
3.7.14 GR4_RVAL . . . 30
3.7.15 GR_WHERE . . . 31
3.7.16 GR8_TRI . . . 31
3.7.17 GR8_SORT . . . 31
3.7.18 GR_CLIP . . . 31
3.8 The cursor routine . . . 31
3.9 **GreG** High-Level Subroutines . . . 32

**4 Task Programming Manual** **36**
4.1 General Outline and Data Structure of Images . . . 36
4.2 Image Slot Handling . . . 37
4.3 Image Connection . . . 38
4.4 Memory Connection . . . 39
4.5 Image Header Access . . . 40
4.5.1 Outline . . . 40
4.5.2 Named Common Description . . . 40
4.6 Basic Header Handling . . . 42
4.7 Named Commons Handling . . . 43
4.8 Creating GILDAS Tasks . . . 43
4.9 A Template Task . . . 44
4.9.1 Source code . . . 44
4.9.2 Initialization file . . . 47
4.9.3 Checker File . . . 48
4.9.4 The HELP file . . . 48
4.10 Debugging Tasks . . . 49

**5 GTVIRT Programming Manual** **50**
5.1 Concept . . . 50
5.2 Programming . . . 51
5.3 Basic Sequence . . . 52
5.4 Plot Structuration and multi-window applications . . . 52
5.5 Subroutines . . . 53

# 1 Introduction

The **GILDAS** programming manual includes all necessary information to create applications based on the **GILDAS** tools. The tools includes:

- **SIC** the command line interpretor, written in FORTRAN and callable as a subroutine by any program.
- **GreG** the high level Graphic library.
- Independent *Tasks* for specific applications. The *Task* programming section describes how to create new **GILDAS** tasks.

The **GTVIRT** low level Graphic library is also described for completeness, although very few programs will actually require using its possibilities directly.

This manual contains several chapters. Chapter 2 (the **SIC** programming manual) is essential when constructing interactive applications. Chapter 3 (the **GreG** programming manual) is essential for all graphics applications. To create tasks, the user only needs to read Chapter 4 (the **GILDAS** task programming manual). Sophisticated graphic application may require to read Chapter 5, the **GTVIRT** programming manual.

# 2 SIC Programming Manual

## 2.1 Introduction

**SIC** (*) is a command line interpretor, written in FORTRAN and callable as a subroutine by any program. It provides a command language rather similar to the VAX-VMS DCL language, with the following major features:

- resolution of command abbreviations
- definition of symbols
- macro capabilities with arguments substitution during execution
- log file
- multi-language structure
- loop buffers for repetitive actions
- variables, arithmetic and logical expressions evaluation
- structured logical tests
- error recovery
- stack buffer
- keypad editing of command lines on VT200 compatible devices
- **NEW!: GUI interface on Motif systems**

This section concerns the programmer who wants to use **SIC** as the monitor of a simple or complex, evolutive, documented interactive program. It assumes that the reader is already familiar with all capabilities of **SIC**, so that he should be able to design a program (or better a system) around the **SIC** monitor.

It is in fact essentially a "CookBook" giving a list of recipes to build a program using **SIC**, or interface **SIC** with a preexisting ensemble of routines. Following these recipes should result in a complete success, that is, a program fulfilling the following requirements:

- Works in interactive or batch, reading commands on the logical unit 5 (standard input). This is call `Read Mode`.
- Can be called as a subroutine to execute a single command (`Execute Mode`). In case of error or if a `PAUSE` is encountered, the system switches to Read Mode for interactive error recovery or to read commands after the `PAUSE`.
- Is completed by a library version
- The library version can be used to make another language around it.
- Is portable on Unix-like systems, and MS-Windows (perhaps VMS, too).

The section 2.2 describes the command vocabulary structure, and the initialization sequence of **SIC**. Section 2.3 gives the archetype of the structure of a program using **SIC** as its monitor. Section 2.4 indicates how to write the corresponding `HELP` files. Section 2.5 describes how to retrieve arguments from a **SIC** command line. Section 2.6 indicates how to complete the program so that it can also be a library of routines. Finally, Section 2.7 indicates how to use **SIC** variables, and Section 2.9.1 give all entry points of the **SIC** monitor.

**SIC** programming interface is designed for the Fortran language. Interfacing with C language requires some system dependent precautions concerning argument passing mechanism, in particular for character strings.

## 2.2 Initializing SIC: The Command Language Structure

**SIC** is a multi-language interpretor. Each language must be initialized by means of an appropriate call to the routine SIC_LOAD. This routine has the following calling list:

```
SIC_LOAD(LANG,HELP,MCOM,VOCAB,VERSION)
```

`LANG` is a Character constant (less than 12 characters) which gives the name of the language. `LANG` need not be distinct from the command names, and it must not include the character \ which will appear in the internal `HELP` of **SIC**.`MCOM` is the number of commands and options appearing in the language vocabulary `VOCAB`. All commands in a **SIC** language are `CHARACTER*12` constants in which the first character is a reserved code. Lower case characters are NOT allowed, but the special character "_" may appear. All other special characters have (or may have in the future) some specific meaning in **SIC**.The following is the `DATA` initialization statement of **SIC** itself given as an example of language.

```
      CHARACTER*12 VOCAB(MVOCAB)
      INTEGER SIC_COMMANDS,USER_COMMANDS
      PARAMETER (SIC_COMMANDS=34)
      PARAMETER (USER_COMMANDS=MVOCAB-SIC_COMMANDS)
      DATA VOCAB/
     +  ' BREAK',       ' CONTINUE',    '$DCL',         '/PROCESS',
     +  ' DEFINE',      '/GLOBAL',      ' DELETE',      '/SYMBOL',
     +  '/VARIABLE',    '#EDIT',        ' ELSE',        ' ENDIF',
     +  ' EXAMINE',     '/GLOBAL',      '#EXIT',        ' FOR',
     +  '/WHILE',       '*HELP',        ' IF',          ' LET',
     +  '/NEW',         '/PROMPT',      ' NEXT',        ' ON',
     +  ' PAUSE',       '#QUIT',        '#RECALL',      ' RETURN',
     +  ' SAY',         ' SIC',         '$SYMBOL',      '/INQUIRE',
     +  '*TYPE',        ' @',          USER_COMMANDS*' '/
```

The first character code is interpreted as follow

`<space>` Usual command

`/` Option of the preceding command

`#` Command forbidden in the stack and in procedures. Commands of this type are still written in the Log_File.

`$` Special command which must not be inserted automatically in the stack. Commands of this type are written in the Log_File

`*` Purely informative command, which is only useful in an interactive session. Commands of this type are not written in the Log_File and not inserted in the Stack.

The `*` code can also be used for complex commands using alphanumeric keywords that you wish to expand yourself before saving them in the Log_File and the Stack, or for commands that may require to output several records (See `SIC_INSERT, SIC_LOG` and `SIC_LIRE`). The **GreG** command `DRAW` is an example of this.

The programmer should be careful about deciding what attribute to give to any command. All the options referring to a command must immediately follow it. At initialization time, **SIC** recognizes the options and set up a table of pointers connecting the options to their respective commands. A failure to respect the adequate order results in a very strange vocabulary.

Finally, `VERSION` is a character string which must contain the version number, and may contain the date of last modification, the name of the programmer,... The following example is recommended for optimum presentation (respect the alignment of the date for different languages):

```
VERSION='1.0   21-APR-1984   Programmer Name'
```

In addition to setting the vocabulary, the programmer must decide the program prompt, the log file and the Stack usage. This is entirely optional because **SIC** provides default setups, and it is done using routine

```
SIC_OPT (PROMPT,LOGFILE,MEMORY)
```

where PROMPT is a character string (less than 8 characters) defining the prompt (**SIC** adds automatically the caret > at end of prompt), LOGFILE is a character string defining the Log_File for the session and MEMORY is a logical flag defining the Stack usage. There two modes for Stack usage: the first mode defines the Stack as an internal procedure which is entirely at the disposition of the user (MEMORY=.FALSE.), the second mode defines the stack as an internal Log_File, in which almost all commands (with the restriction in the command code) typed at the top level in Read Mode are automatically written to the Stack (MEMORY=.TRUE.). This mode provides a playback capability for interactive sessions. Modes can be commuted at run time using **SIC** command SIC MEMORY.

Default values are 'SIC', 'LOG' and .TRUE. respectively. Hence, if you use the defaults, the Log_File can also be defined by an assignation to logical name LOG. The call to SIC_OPT is completely effective if placed before any call to SIC_LOAD. Otherwise, only the prompt will be changed.

## 2.3 The Program Structure

In this section a complete example is described. The language name is set to USER, and it is highly recommended to use the same normalization conventions for the subroutine names. The example takes advantage of the multi-language capabilities of the **SIC** monitor by making also the **GreG** system available in addition to the user's commands. The extra code involved is marked by the flag !!GREG!! and can be removed without affecting the user commands.

The list of routines described here is, in current order :

```
USER            The main program
LOAD_USER       The initialization routine (#)
EXEC_USER       To enter Execute Mode. Execute a single
                SIC/USER valid command (may be a call to a
                procedure) and returns (#).
                Switches to Read Mode on an error condition
                (Interactive session only) or if a PAUSE
                is encountered. Switches back to Execute Mode
                with CONTINUE or EXIT.
PLAY_USER       To enter Read Mode with a SIC/USER valid
                command passed as the first thing to do (#)
ENTER_USER      To enter Read Mode (#). Reads commands on the
                logical unit 5. Error recovery is provided for
                interactive sessions only.
RUN_USER        Dispatching program to execute the user commands
COM1            Example of interface between a "simple"
                Fortran subroutine and a SIC command.
US_EXEC         Interface routine for the Library Version
US_ERROR        idem.

(#)     The inclusion of the extra code flagged as !!GREG!! gives
also access to the command of GREG in the three routines EXEC_USER
PLAY_USER and ENTER_USER.
```

In addition, the "true" library mode is accessible by calling US_EXEC, which is described completely in Section 2.6. This is a complete example which really contains all the relevant structure. The rules for building conventional names are quite obvious.

The following source program available in VMS GAG_UTIL:SICUSER.FOR, and UNIX $GAG_REF/help/sic/sicuser.f)

```
      PROGRAM USER
      INTEGER ICODE,SIC_GET_FOREIGN,LENC,L,NL,SIC_PURGE
      CHARACTER*80 FILE,COMMAND,CHAIN,NAME*12
      CHARACTER BACKSLASH*1
      LOGICAL EXIST
*
* Optionally, get the Foreign argument.
      ICODE = SIC_GET_FOREIGN(COMMAND,NL)
      IF (MOD(ICODE,2).EQ.0) CALL SYSEXI(ICODE)
* Build the names of the log file.
      NAME = 'user'
      CALL SIC_PARSEF (NAME,FILE,'GAG_LOG:','.log')
* Purge older versions of the log file
      ICODE = SIC_PURGE (FILE,1)
      IF (MOD(ICODE,2).EQ.0) CALL SYSEXI(ICODE)
*
* Initialize the command monitor with a nice Prompt, and stack capability
      NAME = 'USER'
      CALL SIC_OPT(NAME,FILE,.TRUE.)
* Then load all languages
      CALL LOAD_USER
* Demonstration of multi-language capabilities
      CALL LOAD_GREG('LIBRARY')          !!GREG!!
* Define a default macro extension
      CHAIN = 'SIC'//BACKSLASH//'SIC EXTENSION .user'
* Execute the "login" macro
      NAME = 'init'
      CALL SIC_PARSEF (NAME,FILE,'GAG_INIT:','.user')
      L = LENC(FILE)
      INQUIRE (FILE=FILE(1:L),EXIST=EXIST)
      IF (EXIST) THEN
         CHAIN = '@ ``!''//FILE(1:L)//''''
         CALL EXEC_USER (CHAIN)
      ENDIF
* Activate the monitor
      IF (NL.NE.0) THEN
* First executing the foreign argument if available
         CALL PLAY_USER(COMMAND(1:NL))
      ELSE
* Or not
         CALL ENTER_USER
      ENDIF
      END



      SUBROUTINE LOAD_USER
      INTEGER MCOM
      PARAMETER (MCOM=3)
```

```
      CHARACTER*12 VOCAB(MCOM)
      DATA VOCAB / ' COM1' , '/GAG' , ' COM2' /
      CALL SIC_LOAD('USER','GAG_HELP:sicuser.hlp',MCOM,VOCAB,
     &    '4.0    24-AUG-1984')
      END
```

The example shows how to retrieve a first command from the operating system at run time (SIC_GET_FOREIGN), how to define a default macro extension, and how to execute the user initialization macro if it exists. Two types of complete calls to the SIC/USER system are demonstrated.

```
      SUBROUTINE EXEC_USER(BUFFER)
      LOGICAL ERROR
      CHARACTER*(*) BUFFER
      CHARACTER LINE*256, COMM*12, LANG*12
      INTEGER ICODE,OCODE
*
      LINE = BUFFER
      ICODE = -1
      GOTO 10
*
      ENTRY PLAY_USER(BUFFER)
      LINE = BUFFER
      ICODE = 2
      GOTO 10
*
      ENTRY ENTER_USER
      ICODE = 1
      GOTO 10
*
* Call the monitor again after completion of every user command.
10    CALL SIC_RUN (LINE,LANG,COMM,ERROR,ICODE,OCODE)
      IF (OCODE.EQ.0) THEN
         IF (LANG.EQ.'USER') THEN
            CALL RUN_USER (LINE,COMM,ERROR)
         ELSEIF (LANG.EQ.'GREG1') THEN !!GREG!!
            CALL RUN_GREG1 (LINE,COMM,ERROR) !!GREG!!
         ELSEIF (LANG.EQ.'GREG2') THEN !!GREG!!
            CALL RUN_GREG2 (LINE,COMM,ERROR) !!GREG!!
         ELSEIF (LANG.EQ.'GTVL') THEN !!GREG!!
            CALL RUN_GTVL  (LINE,COMM,ERROR) !!GREG!!
            IF (COMM.EQ.'CLEAR') CALL GRESET !!GREG!!
         ELSE
            WRITE(6,*) 'Unrecognized Language ',LANG
            ERROR = .TRUE.
         ENDIF
      ELSEIF (OCODE.EQ.-1) THEN
* Must return immediately from the Execute Mode,
         RETURN
      ELSEIF (OCODE.EQ.1) THEN
* Any other code may be added before returning to the main program
         RETURN
      ENDIF
      ICODE = 0
```

```
      GOTO 10
      END
```

In the Execute Mode, all **SIC** capabilities are enabled. A more restrictive Library Mode, in which only the command line interpretor of **SIC** is used will be shown in Section 2.6

```
      SUBROUTINE RUN_USER(LINE,COMM,ERROR)
      CHARACTER*(*) LINE,COMM
      LOGICAL ERROR
*
* Call appropriate subroutine according to COMM
      IF (COMM.EQ.'COM1') THEN
         CALL COM1(LINE,ERROR)
      ELSEIF (COMM.EQ.'COM2') THEN
         WRITE (6,*) 'Command COM2 activated'
*        CALL COM2(LINE,ERROR)
      ENDIF
      END

      SUBROUTINE COM1(LINE,ERROR)
      CHARACTER*(*) LINE
      LOGICAL ERROR
      LOGICAL SIC_PRESENT
      INTEGER IARG1_OPT1
      REAL ARG1
*
* Test presence of option 1, and if so
*       Decode Argument 1 of this option with a default value
      IF (SIC_PRESENT(1,0)) THEN
          IARG1_OPT1 = 10
          CALL SIC_I4 (LINE,1,1,IARG1_OPT1,.FALSE.,ERROR)
          IF (ERROR) RETURN
          WRITE (6,*) 'Option 1 Set With Argument',IARG1_OPT1
      ENDIF
*
* Retrieves and decode first argument of the command
      CALL SIC_R4 (LINE,0,1,ARG1,.TRUE.,ERROR)
      IF (ERROR) RETURN
      WRITE (6,*) 'Command COM1 activated. ARG1',ARG1
* End of interface analysis, call a standard FORTRAN routine with
* all parameters now defined
*     CALL SUB1(ARG1,ARG2,...,IARG1,...,ERROR)
      RETURN
      END
```

As in this example, it is HIGHLY RECOMMENDED to pass the command buffer `LINE` by argument and NOT IN A COMMON. This will allow later an easy implementation of a multi-language program if necessary, and the possibility of sharing languages with other users. Use of commons may break these possibilities. It is also recommended to have an "interface" routine for each command which takes all the decoding functions. However, for very simple commands, this may not be necessary and the interface may be in the `RUN_USER` routine.

## 2.4 The Help File

The HELP files are simple text files with two levels of help. The list of help topics in the library should be identical to the list of commands of the program. In addition, a specific topic named LANGUAGE should include a one line description of all commands, with a subtopic named NEWS which describe the latest news on the specific language.

The HELP files format is the following

```
1 TOPIC
    help for this topic
2 SUBTOPIC
    help for a subtopic of the previous topic
1 OTHER_TOPIC
    text for other_topic
1 END
```

where 1 and 2 are in the first column of the text file, and followed by a single space. This format is easy to modify as it is a simple text file, but much slower to access because it is sequential. The `1 END` (with no trailing characters) sequence indicates the end of the help file.

The help file name should be assigned to the logical name specified in the SIC_LOAD call, or given explicitly.

## 2.5 Retrieving Arguments

To properly interface your program, you must know how to retrieve an argument from the command buffer processed by **SIC**In standard **SIC** offers for each command up to 98 options, and for each option (or command) up to 98 arguments, the total number of arguments and options in a command line being limited to 99.

Arguments in **SIC** command lines are positional. The position of argument number IARG of option number IOPT of the current command is kept in **SIC** by means of internal pointers, By convention, argument number 0 refers to the option (or command) itself, and option number 0 to the command itself. Four standard routines are provided to decode the following type of arguments. All these routines do not modify the value of the argument if it is missing in the command buffer. They may return an error condition and output an error message if requested in this case.

```
Argument Type   Routine Name
Integer*4         SIC_I4
Real*4            SIC_R4
Real*8            SIC_R8
Logical*4         SIC_L4
Character         SIC_CH
Character         SIC_KE          (Upcase converted keyword)
```

The first four routines routines have the following calling list

```
      CALL SIC_name (LINE,IOPT,IARG,Arg,PRESENT,ERROR)
in which
      LINE        The command buffer
      IOPT        The option number (0=command)
      IARG        The argument number (0=command or option)
      Arg         The argument to be retrieved
      PRESENT     A flag indicating whether an error must occur if
                  the argument is not present in the command line
      ERROR       An error flag set in case of decoding errors,
```

```
                    or for missing argument when PRESENT is set.
```

SIC_CH and SIC_KE are slightly different, because they also return the length of the character string:

```
          CALL SIC_CH (LINE,IOPT,IARG,Arg,Larg,PRESENT,ERROR)
          CALL SIC_KE (LINE,IOPT,IARG,Arg,Larg,PRESENT,ERROR)
where
          Larg        Integer, true length of Arg
```

While SIC_CH returns any character string, with implicit formatting if necessary, but no case conversion, SIC_KE returns upcase keywords.

Two additional routines provide a way of testing the presence of an argument SIC_PRESENT(IOPT,IARG) returns the logical value .TRUE. if the required argument is present, and SIC_LEN(IOPT,IARG) returns the actual length of the argument (0 means the argument is missing). A last routine, SIC_NARG(IOPT) indicates how many arguments are actually present for option IOPT.

Note that due to the structure of **SIC** vocabulary, IOPT is always the sequential number of the option as defined by the ordering in the DATA statement. Hence IOPT is not dependent on the order in which the options appear in the command buffer currently analysed.

**SIC** also includes some general character string manipulation routines which may be of interest in many other problems. All these routines are described more completely in section 2.9.1.

## 2.6 The Library Version

### 2.6.1 Creating the Library Interface

Once you have completed the previous operations, an interactive system is available. The system can also be used in batch or within command procedures. It is very easy to make a Fortran callable version of this system by adding only one extra subroutine. Taking again the same example this subroutine will be:

```
      FUNCTION US_ERROR(dummy)
*
*       Library version of the user program.
*       All the user commands are accessible through calls
*       in the form:
*
*       CALL US_EXEC ('This_command')
*
*       The error status can be checked and reset using the
*       function US_ERROR(). If an error exist, the program
*       aborts when trying to execute the next command.
*
      INCLUDE 'inc:errcod.inc'
* The above line defines the FATALE error code used below
      LOGICAL ERROR, US_ERROR
      CHARACTER*(*) BUFFER
      CHARACTER LINE*256, COMM*12, LANG*12, MESSAGE*60
      INTEGER NL, DUMMY, LENC
* Save the error code from last call
      SAVE ERROR
*
* Transmit error status, and reset it
      US_ERROR = ERROR
      ERROR = .FALSE.
      RETURN
```

```
*
      ENTRY US_EXEC(BUFFER)
*
* Check error status, abort if not cleared
      IF (ERROR) THEN
         WRITE(6,*) MESSAGE
         WRITE(6,*) LINE(1:NL)
         CALL SYSEXI (FATALE)
      ENDIF
*
* Copy the command line in argument to the local buffer LINE
* Format it and Analyse it
      LINE = BUFFER
      NL=LENC(LINE)
      CALL SIC_FORMAT (LINE,NL)
      CALL SIC_ANALYSE(COMM,LINE,NL,ERROR)
      IF (ERROR) THEN
         MESSAGE = 'E-US_EXEC,  Error Interpreting Line'
         RETURN
      ENDIF
*
* If your application is multi-language, then make sure that the
* command belongs to your language.
      CALL SIC_LANG(LANG)
      IF (LANG.NE.'USER') THEN
         ERROR = .TRUE.
         MESSAGE = 'E-US_EXEC,  Language Mismatch Line'
         RETURN
      ENDIF
*
* Execute it
      CALL RUN_USER(LINE,COMM,ERROR)
      IF (ERROR) THEN
         MESSAGE 'E-US_EXEC,  Error Executing Line'
      ENDIF
      END
```

A program can then be written just by typing the same commands as in interactive. Of course, this is not always convenient, but you should be able to provide additional routines to make the formatting of the line, or give a more direct argument transmission. Note that all errors are absolutely fatal in this Library Mode, and must be handled by the calling program. This is in contrast with the `EXEC_USER` routine which provided a **SIC** like error recovery, but at the expense of a compulsory interactive use of the program.

### 2.6.2 Library Only Mode

It is sometimes a burden to have complex languages such as `GREG1\` in your `HELP` when you just want to use the library version of the language. **SIC** provides a way to load a language in "Library Only" mode. This means that the commands are accessible only through a `US_EXEC` like program and not through **SIC** monitor capabilities. This mode is useful for building another more elaborate language from one (or more) lower level languages (pay attention to possible recursive programming in doing so however). This mode is called by loading the corresponding language with a null help specification :

```
SIC_LOAD(LANG,' ',MCOM,VOCAB,VERSION)
```

### 2.6.3 Reserved logical unit numbers: VMS

**SIC** has the following usage of Fortran logical unit numbers:

```
5        Input of Commands, shareable
6        Output of messages, shareable
```

Units 5 and 6 are respectively accessed via usual `READ` and `WRITE` instructions. In addition, the terminal is accessed via `QIO` on an assigned channel for keypad line editing. The associated logical names are `FOR005` and `FOR006` and the default assignments provided by the system VMS are:

```
ASSIGN SYS$INPUT FOR005
ASSIGN SYS$OUTPUT FOR006
```

If you wish to be able to reassign the input or/and output of your program to a file, you should also make your input and output in the same way (or use the `SIC_WPR, SIC_WPRN` routine). If you mix `READ(5,format)` and `WRITE(6,format)` instructions with `TYPE, ACCEPT, READ(*,format) or WRITE(*,format)` instructions, you might experience some problems to properly re-assign input or output. As a hint for this, remember the default logical names for Input/Output on VAX/VMS :

| Statement | Fortran Log Name | System Log Name |
|---|---|---|
| READ(nnn,f) list | FORnnn | SYS$INPUT |
| READ(*,f) list | FOR$READ | SYS$INPUT |
| READ(f) list | FOR$READ | SYS$INPUT |
| ACCEPT f,list | FOR$ACCEPT | SYS$INPUT |
| WRITE(nnn,f) list | FORnnn | SYS$OUTPUT |
| WRITE(*,f) list | FOR$PRINT | SYS$OUTPUT |
| PRINT f,list | FOR$PRINT | SYS$OUTPUT |
| TYPE f,list | FOR$TYPE | SYS$OUTPUT |

The monitor uses additional logical units for the `LOG` file, for opening temporary files and for active macro's. These units are reserved dynamically by calls to the VAX-VMS appropriate services and do not interfere with any Fortran unit numbers used within the user program, except that a program may use too many logical units.

### 2.6.4 Reserved logical unit numbers: UNIX

**SIC** has the following usage of Fortran logical unit numbers:

```
5        Input of Commands, shareable
6        Output of messages, shareable
50 to 99 Used by SIC_GETLUN
```

Units 5 and 6 are respectively accessed via usual `READ` and `WRITE` instructions. If you wish to be able to reassign the input or/and output of your program to a file, you should also make your input and output in the same way (or use the `SIC_WPR, SIC_WPRN` routine). If you mix `READ(5,format)` and `WRITE(6,format)` instructions with `PRINT, READ(*,format) or WRITE(*,format)` instructions, you might experience some problem. Mixing with `C` output (`printf` routine for example) may yield to disordered output because of buffering. Use of routine `GAGOUT` is recommended to printout messages.

Units 50 to 99 are assumed to be available for the routine `SIC_GETLUN` . This subroutine returns the next available logical unit in this range, and keeps track of their usage. Conflict may occur if the user directly opens a file under a unit in this range without allocating the unit through a call to `SIC_GETLUN`. Other units are never used by **SIC** and other **GILDAS** programs.

### 2.6.5 Linking on VMS

In order to avoid an overhead in program size and link time, the **SIC** system takes advantage of the shareable library facilities. All the **SIC** system is contained in the module `SICSHR` available in the library `GAG_ROOT:[SHARED]GAGSHARE.OLB`.

The access to this library is automatic on some computers. Issue the command
`$ SHOW LOGICAL LNK$LIB*`
to know if automatic linking is enabled.

If not enabled, you may either make an explicit reference in the link as:
`$ LINK PROG1,PROG2,...,GAG_ROOT:[SHARED]GAGSHARE/LIB`
either add the following assignment in your LOGIN.COM for automatic linking to this library:
`$ ASSIGN GAG_ROOT:[SHARED]GAGSHARE.OLB LNK$LIBRARY`
Note that is you wish to use the **GreG** library together with **SIC** you must also reference the library `GAG_ROOT:[SHARED]GREGLIB.OLB` as described in the **GreG** manual.

### 2.6.6 Linking on UNIX

On Unix system, the location of the GAG software environment is normally defined by the `$GAG_ROOT` environment variable. If not, ask your system manager to add the definition of `$GAG_ROOT` in a system-wide "login" script.

Several libraries are needed to run the **SIC** system. Libraries may be shareable or simple archive: the operating system will normally decided which one to use. All libraries are in the directory `$GAG_ROOT/lib`. The link command should look like (e.g. for Fortran program on HP-UX systems):

```
fort77 -L$GAG_ROOT/lib -o prog prog.o -lsic -limage -lgag -lrary
```

Other compilers (such as `cc`, the `C` compiler) will have similar options, but note however that the Fortran libraries will be needed in the link. Beware that the order of the libraries is significant. For systems not supporting the `-L` option, you will have to explicitly mention the full names of the libraries.

## 2.7 Using Variables

**SIC** allows the definition and use of variables. Variables can be declared by the user, or by the program. In the latter case, **SIC** only remembers the address of the variable, examining its content only when required (command `EXAMINE` for example or any reference to the variable name in a command). This imposes two precautions in the FORTRAN code.

1. The attribute of the **SIC** variable (`READ-ONLY` or `READ-WRITE`) should be chosen carefully (e.g. a real-time application in which the time is declared as a **SIC** variable).
2. The corresponding FORTRAN variable must be `SAVE`d (or appear in a `SAVEd COMMON`) to prevent the compiler to allocate it on the stack.

### 2.7.1 Definition

There are 5 variable declaration routines following the same calling conventions

```
          Argument Data Type      Name of Subroutine
                REAL*8                  SIC_DEF_DBLE
                REAL*4                  SIC_DEF_REAL
                INTEGER*4               SIC_DEF_INTE
                CHARACTER*(*)           SIC_DEF_CHAR
                LOGICAL*4               SIC_DEF_LOGI

The calling syntax is the following
          CALL SIC_DEF_Name (NAME,VARIABLE,READONLY,ERROR)
for LOGI and CHAR, and
          CALL SIC_DEF_Name (NAME,VARIABLE,NDIM,DIM,READONLY,ERROR)
for DBLE, REAL, and INTE, NDIM being the number of dimensions,
and DIM the dimensions of the array VARIABLE.
```

NAME is the name of the **SIC** variable, VARIABLE the name of the corresponding FORTRAN variable, READONLY a logical indicating whether the variable should be Read-Only (.TRUE.) or Read-Write (.FALSE.). ERROR is a logical error flag set by **SIC** if the variable could not be defined.

Variable names must be at most 15 characters, upper case only, and beginning with a letter. Special characters must be avoided, except the "_" (underscore) sign.

### 2.7.2 Assignment and Examination

**SIC** variables can be assigned new values, and examined using the following routines.

| Argument Data Type | Assignment | Examination Subroutine |
|---|---|---|
| REAL*8 | SIC_LET_DBLE | SIC_GET_DBLE |
| REAL*4 | SIC_LET_REAL | SIC_GET_REAL |
| INTEGER*4 | SIC_LET_INTE | SIC_GET_INTE |
| LOGICAL*4 | SIC_LET_LOGI | SIC_GET_LOGI |
| CHARACTER*(*) | SIC_LET_CHAR | SIC_GET_CHAR |

```
The calling syntax is the following
          CALL SIC_LET_Name (NAME,VARIABLE,ERROR)
          CALL SIC_GET_Name (NAME,VALUE,ERROR)
except for SIC_GET_CHAR
          CALL SIC_GET_CHAR (NAME,STRING,LENGTH,ERROR)
```

These a-priori useless routines can be used to modify variables defined in completely independent parts of a program such as the codes supporting two different **SIC** languages. For example the GRAPHIC\ language interacts with GREG1\ and GREG2\ through **SIC** variables.

For assignment routines, the data type of the VARIABLE argument and of the **SIC** variable must match exactly. For retrieving routines, the data type to specify is the type of the VALUE argument; implicit conversion from the type of the **SIC** variable is done if possible, an error is returned otherwise.

Only SCALAR variables can be assigned or examined in this way. For ARRAY variables, you should use the subroutine SIC_DESCRIPTOR.

```
          CALL SIC_DESCRIPTOR (VARIABLE,DESC,FOUND)

   - VARIABLE is the variable name (general syntax A[i,j] allowed)
   - DESC is the descriptor of the variable, an integer array of
     dimension 9 containing
        DESC(1) Variable type, with READONLY code. The true
                variable type is VAR_TYPE(DESCR)
                Valid values are
                * 0 < VAR_TYPE(DESC) : Character string of length
                                       VAR_TYPE(DESC)
                * VAR_TYPE(DESC) < 0 may have the value
                      FMT_R4 for REAL*4 variable
                      FMT_R8 for REAL*8 variable
                      FMT_I4 for INTEGER*4 variable
                      FMT_L  for LOGICAL*4 variable
                      FMT_BY for BYTE variable
                      FMT_C4 for COMPLEX variables
                * If VAR_TYPE(DESC) is not equal to DESC(1), the
                      variable is READONLY.
        DESC(2) Variable address
        DESC(3) Number of dimensions
        DESC(4) - DESC(7)     Dimensions
```

```
        DESC(8) Size of allocation (words)
        DESC(9) Origin of variable
                0       program defined
                < 0     user defined
                > 0     image
    - FOUND is a logical indicating whether the specified variable
      exist or not.
```

The parameters FMT_R4, FMT_R8, FMT_I4, FMT_L, FMT_BY and FMT_C4 are defined in the file inc:format.inc.

Two other routines may be required for variable handling:

SIC_INCARNATE is used to create an "incarnatio" of a variable under a specified type (REAL, DOUBLE, INTEGER).

```
        CALL SIC_INCARNATE(FORM,DESC,INCA,ERROR)
where
    - FORM is the format of the desired incarnation (FMT_R4, FMT_I4
      or FMT_R8)
    - DESC is the descriptor of the variable
    - INCA is the descriptor of the incarnation
    - ERROR is a logical error flag
```

DESC and INCA are Integer arrays of dimension 9. DESC should have been obtained by a previous call to SIC_DESCRIPTOR.

Once used, the incarnation may be deleted using routine SIC_VOLATILE

```
    CALL SIC_VOLATILE(INCA)
where
    - INCA is the descriptor of the incarnation.
```

### 2.7.3 Mathematical Formula Handling

Two subroutines are available to decode mathematical or logical expressions, SIC_MATH and SIC_LOGICAL. In addition, a subroutine is available to decode generalized sexagesimal notation, SIC_SEXA. The calling syntax is the following

```
CALL SIC_name (EXPRESSION,LENGTH,VARIABLE,ERROR)
```

where EXPRESSION is a character string containing the mathematical or logical expression to be evaluated, LENGTH is the number of characters of this expression, VARIABLE a REAL*8 (or LOGICAL*4) variable to receive the expression value, and ERROR a logical error flag. A generalized sexagesimal notation is for example A:B:C or A:B, where A, B and C may be variables or expressions or numbers. B and C values must of course be greater than or equal to 0 and less than 60. The value is returned in units of A, the leftmost field.

### 2.7.4 Deleting Variables

Declared variables can be deleted when no longer needed, using routine SIC_DELVARIABLE. The calling syntax is the following

```
CALL SIC_DELVARIABLE (NAME,USER,ERROR)
```

where NAME is the **SIC** variable name, USER a logical indicating whether program-defined variable are protected against deletion (.TRUE.) or can be deleted (.FALSE.), and ERROR a logical error flag.

## 2.8 Using Functions

It is possible to define user callable functions which are recognized in the mathematical formulae evaluations, using subroutine SIC_DEF_FUNC as follows

```
    CALL SIC_DEF_FUNC(NAME,SF,DF,NARG,ERROR)
where
    NAME  is the function name
    SF    is the address of the single precision implementation of
          the function
    DF    is the address of the double precision implementation of
          the function
    NARG  is the number of arguments of the function.
    ERROR is an error flag
```

Both single and Double precision routines will be called like as (e.g. for two arguments)

```
    S = SF(arg1,arg2)      and      D = DF(arg1,arg2)
```

## 2.9 SIC Callable Routines

### 2.9.1 Monitor interface routines

```
Available subroutines:
        SIC_LOAD        SIC_OPT         SIC_RUN
        SIC_INSERT      SIC_LOG         SIC_LANG
Available functions:
        SIC_CTRLC       SIC_LIRE        SIC_INTER_STATE
```

To build a program around the **SIC** monitor, different routines are provided. Some must always be used (SIC_LOAD and SIC_RUN), others are simply provided for additional capabilities. These routines have a standard SIC_ like name and are fully described in this section.

SIC_RUN (LINE,LANG,COMMAND,ERROR,ICODE,OCODE)

This subroutine is used to enter SIC, retrieve and analyse a command line for further execution. All **SIC** possibilities, including execution levels and error recoveries, made accessible (In particular, the LINE command line can be a call to a macro file).

- LINE Character*(*) (maximum size is 2048)
  Command line to be executed. Modified by **SIC**No need to initialize it when ICODE = 0 or 1, but must be initialized is ICODE = -1 or 2
- LANG Character*12
  Name of the language returned by **SIC**
- COMMAND Character*12
  Name of the command returned by **SIC**
- ERROR Logical
  Return error code
- ICODE Operation code
  - ICODE = -1
    Analyse the command line passed as argument LINE, and return to calling program to execute it.

  - ICODE = 0
    Loop into SIC to retrieve a new command line LINE, and return to calling program to execute it.
  - ICODE = 1
    Start SIC, and retrieve a first command line.
  - ICODE = 2
    Start SIC, analyse the command line passed as argument, and return to calling program to execute it.

- `OCODE Return code`

  - OCODE = -1
    End of execution in sub-routine mode. Program must return immediately to its caller.
  - OCODE = 0
    Successful analysis of a command. Program must execute it, and then loop again on `SIC_RUN` with ICODE=0 to get further commands.
  - OCODE = 1
    End of execution caused by typing the EXIT command. Program should perform any necessary action (close files, etc...) and return to its caller.

`SIC_LOAD (LANG,HELP,NCOM,CCOM,VERSION)`
This subroutine initialize a **SIC** language and thus is usually the first one called. All arguments are unchanged by the routines and may be passed as immediate values.

- `LANG Character*(*).`
  The language name, as it will appear in the `HELP` and will be returned by **SIC** after command line processing. It is truncated to 12 characters if necessary.

- `HELP Character*(*).`
  The logical name for the `HELP` file corresponding to the language being initialized.

- `NCOM Integer.`
  The number of command and options, i.e. the dimension of the `CCOM` character array

- `CCOM Character*12 array of dimension NCOM.`
  Contains the vocabulary of the language. The structure of the command vocabulary is described elsewhere in this document.

- `VERSION Character*(*).`
  A string to indicate the version number, the last modified date, the programmer name,... which will appear as a message with the language name at run time.

`SIC_OPT (PROMPT,LOGFILE,MEMORY)`
This routine is not compulsory. It is used to set the prompt the log file name and the stack usage. This routine only changes the prompt if called after `SIC_LOAD`.

- `PROMPT Character*(*).`
  The prompt to be used in interactive mode, truncated to 8 characters if necessary. Default is `SIC`. Note that the caret `>` and other alterations such as : or `_1>` are added by **SIC** at run time and should not be included.

- `LOGFILE Character*(*).`
  The log file name. Default is `LOG`.

- `MEMORY Logical.`
  Indicates whether the Stack is used or not.

SIC_INSERT(LINE)

This routine is only useful when the Stack Buffer is used to store commands. This is the default, and the case when the flag MEMORY was set to .TRUE. in the first call to SIC_OPT. It can be changed with the SIC MEMORY command. SIC_INSERT is used to put a command line into the Stack buffer, a very useful possibility for some applications, when several lines must be put or when the command line must be expanded by the user program before the insertion is made.

Note however that command lines are automatically inserted in the Stack Buffer by the monitor for usual commands. This is the standard way of using the Stack insertion mode, since it automatically takes into account many things like the execution level before deciding whether an insertion must occur. Using directly SIC_INSERT usually implies to disable the automatic insertion by the monitor (using the character code * in the definition of the associated command, c.f. Section 2.2). You need also to perform a call to SIC_LIRE to check the **SIC** execution mode (you should only call SIC_INSERT when SIC_LIRE() is equal to 0) and associated calls to SIC_LOG to write the same information in the LOG file. The insertion does not occur if the memory flag is turned off (SIC MEMORY OFF).

- LINE Character*(*).

SUBROUTINE SIC_LOG (LINE,NL,LIRE)

This subroutine writes LINE(1:NL) into the Log_File if LIRE=0. LIRE is here necessary for consistency with the internal pointer indicating if **SIC** is processing a macro, the stack or the loop. This pointer can be retrieved by the function SIC_LIRE. A call to SIC_LOG when LIRE is not 0 has no action.

- LINE Character*(*) Input
- NL Integer Input
- LIRE Integer Input

SUBROUTINE SIC_LANG(LANG)

This subroutine returns the name of the language corresponding to the last command analysed. It is called only when building the library version of a multi-language application.

- LANG Character*(*) is returned by the routine

LOGICAL FUNCTION SIC_CTRLC ( )

**SIC** itself traps the <^C> by generating a PAUSE at the end of the command which was being executed when <^C> was pressed. You may want in time-consuming applications to check yourself at specific points whether <^C> has been pressed. SIC_CTRLC allows you to do so, and resets an internal flag to .FALSE. when called. It returns .TRUE. if <^C> has been pressed since either the last command completed execution or the last time it was called (using the most recent event), .FALSE. otherwise.

INTEGER FUNCTION SIC_LIRE ( )

This subroutine returns the internal pointer of **SIC** indicating where **SIC** is currently reading its commands. SIC_LIRE may take the values

- -10 Subroutine mode
- -2 Reading in the Loop buffer
- -1 Called from SIC_RUN with ICODE = -1
- 0 Interactive mode
- I>0 Reading in macro number I

LOGICAL FUNCTION SIC_INTER_STATE ( )

This subroutine returns .TRUE. if the session is interactive, .FALSE. otherwise. This is the case if **SIC** is ran during a batch process, or if the logical unit FOR005 is assigned to a file (either directly or through an assignment of SYS$INPUT).

### 2.9.2 SIC Arguments Retrieving Routines

```
Available subroutines:
          SIC_L4          SIC_I4          SIC_R4          SIC_R8
          SIC_CH          SIC_KE          SIC_NEXT

Available functions:
          SIC_PRESENT     SIC_LEN         SIC_NARG        SIC_START
```

There are 5 retrieving routines following similar calling conventions

```
          Argument Data Type      Name of Subroutine
                REAL*8                  SIC_R8
                REAL*4                  SIC_R4
                INTEGER*4               SIC_I4
                LOGICAL*4               SIC_L4
                CHARACTER*(*)           SIC_CH, SIC_KE
```

```
The calling syntax is the following
          CALL SIC_Name (LINE,IOPT,IARG,ARGUM,PRESENT,ERROR)
Except for SIC_CH and SIC_KE
          CALL SIC_CH   (LINE,IOPT,IARG,ARGUM,LARG,PRESENT,ERROR)
          CALL SIC_KE   (LINE,IOPT,IARG,ARGUM,LARG,PRESENT,ERROR)
```

- `LINE Character*(*)`
  is the last command line processed from which arguments are to be retrieved.
- `IOPT Integer`
  is the number of the option. 0 means the command. Options are numbered in the order where they appear in the vocabulary array after the command name.
- `IARG Integer`
  is the number of the argument of the option/command to be retrieved. 0 means the option/command itself.
- `ARGUM (Type depending on the subroutine called)`
  is the argument to be returned
- `LARG Integer`
  is the returned number of characters for `SIC_CH` and `SIC_KE`
- `PRESENT Logical`
  is a logical indicating whether the argument must be present `(.TRUE.)` or not `(.FALSE.)`.
- `ERROR An logical error flag`
  which is set if either i) `PRESENT` = `.TRUE.` and the argument is missing or ii) a decoding error occured.

In addition there are other functions related to the arguments: `INTEGER FUNCTION SIC_NARG(IOPT)`
returns the number of arguments present for option `IOPT`.
`LOGICAL FUNCTION SIC_PRESENT(IOPT,IARG)`
returns a logical value indicating the presence of the `IARG-th` argument of the `IOPT-th` option.
`SUBROUTINE SIC_AMBIGS(FACILITY,NAME,FULL,VOCAB,MVOC,IVOC,ERROR)`
search for `NAME` in the vocabulary `VOCAB`, and returns the corresponding pointer `IVOC` in the vocabulary and corresponding keyword `FULL = VOCAB(IVOC)` if `NAME` is a non-ambiguous abbreviation of `FULL`.

- FACILITY Character*(*)
  A character string containing the name of the calling subroutine. This string is printed before any failure message (ambiguous or non existing keyword).
- NAME Character*(*)
  The input name to be searched for in the vocabulary
- FULL Character*(*)
  The complete keyword returned.
- IVOC Integer
  The keyword number in the vocabulary.
- MVOC Integer
  The number of keywords in the vocabulary.
- VOCAB Character*(*)(MVOC)
  The vocabulary.
- ERROR Logical
  An error flag set if the input name was ambiguous, invalid or not found in the vocabulary.

INTEGER FUNCTION SIC_LEN(IOPT,IARG)
returns the total length of the IARG-th argument of the IOPT-th option. Returns 0 if SIC_PRESENT(IOPT,IARG)=.FALSE.

INTEGER FUNCTION SIC_START(IOPT,IARG)
returns a pointer to the address of the argument in the character string. Returns 0 if SIC_PRESENT(IOPT,IARG)=.FALSE.. This routine can be used with SIC_LEN for special processing of arguments, such as sexagesimal decoding.

SUBROUTINE SIC_NEXT(LINE(NEXT:),ARGUM,LARG,NEXT)
This subroutine can be used for special processing of text with a syntax similar to command lines, i.e. text in which the delimiters are single spaces, strings being included between double quotes. Provided it is called with the text restricted to the current delimiter position LINE(NEXT:), it returns the position of the next delimiter NEXT (space, skipping strings), the character string included between these delimiters, ARGUM and its length LARG. This string may further be decoded as double precision value using routine SIC_MATH or SIC_SEXA, logical value using routine SIC_LOGICAL, or used as character constant.

### 2.9.3 Command Line Interpretor Subroutines

SUBROUTINE SIC_ANALYSE (COMMAND,LINE,NLINE,ERROR)
This subroutine analyses the command line LINE, set up all the internal pointers for argument retrieval, and returns the name of the command found. The line must have been formatted by SIC_FORMAT before being analysed. All active languages are considered, even the "Library Only" languages

- COMMAND Character*12, Command name (returned)
- LINE Character*(*), Line to be analysed. It is modified by SIC_ANALYSE
- NLINE Integer. Current length of LINE, modified on return.
- ERROR Logical. Return error code

SUBROUTINE SIC_FORMAT(LINE,NLINE)
This subroutine does an adequate formatting of any line for later processing by the **SIC** interpretor. It does not use any internal common of **SIC** and thus may be accessed independently and considered as a more general routine.

- LINE Character*(*), Line to be formatted.
- NLINE Integer, Current length of LINE. It is modified by SIC_FORMAT and must be initialized so that only trailing spaces appear in LINE after NLINE. A good policy is to initialize NLINE to LENC(LINE).

### 2.9.4 All Purpose General Subroutines

```
Available subroutines:
          SIC_LOWER       SIC_PARSEF      SIC_UPPER       SIC_WPR
          SIC_WPRN
Available functions
          SIC_GETVM       FREE_VM         LENC
```

These routines are of more general use than **SIC** itself.

`INTEGER FUNCTION SIC_GETVM(N32,ADDR)`

`SIC_GETVM` allocates virtual memory for `N32` 32-bit words, and returns the allocated address space into variable `ADDR`. `SIC_GETVM` is set to 1 in case of success, to other values otherwise.

`SUBROUTINE FREE_VM(N32,ADDR)`

`FREE_VM` can be used to free the corresponding adress space when no longer needed.

`SUBROUTINE SIC_LOWER(LINE) - SIC_UPPER(LINE)`

Converts the string LINE to lower or upper case letters respectively.

`SUBROUTINE SIC_PARSEF (NAME,FILE,DEF,EXT)`

Parses the file name `FILE` for a default directory `DEF` and extension type `EXT`. These item are added to `FILE` if needed, and `NAME` returns the short `NAME` of the file, that is, the name without extension or directory. All arguments are Character*(*). This is the standard way to obtain a file name in the **GILDAS** environment: this routine takes care of logical names (in the SIC meaning).

`SUBROUTINE SIC_WPR(PROMPT,LINE)`

Reads the string `LINE` with the prompt `PROMPT`. It tries to obtain a non-blank string, prompting again if it reads a blank string. If it receives a `<^Z>` code, it returns the string `"EXIT"`. The prompt is automatically disabled if the session is not interactive.

- `PROMPT` Character*(*), Unchanged by `SIC_WPR`
- `LINE` Character*(*), Returned line.

`SUBROUTINE SIC_WPRN(PROMPT,LINE,N)`

Reads the string `LINE` with the prompt `PROMPT`. Returns N the number of characters read. Returns N=0 if it reads a blank line, or receives a `<^Z>` code. The prompt is automatically disabled if the session is not interactive.

- `PROMPT` Character*(*), Unchanged by `SIC_WPRN`
- `LINE` Character*(*), Returned line.
- `N` Integer, Number of characters in `LINE`

`INTEGER FUNCTION LENC(LINE)`

Returns the "current" length of the string `LINE`, that is the position of the last significant character. It thus allows to ignore trailing blanks.

### 2.9.5 Symbol Manipulation Routines

Three routines are available to define, translate and delete symbols within a program using **SIC** without using the `SYMBOL` command.

`SUBROUTINE SIC_SETSYMBOL(SYMBOL,TRANSLATION,ERROR)`

Defines a symbol of name `SYMBOL` (Character*(*), maximum 12 characters), translation `TRANSLATION` (Character*(*), maximum 132 characters). An error flag (`ERROR` logical) is returned if the symbol could not be defined. Any previous definition is overridden.

`SUBROUTINE SIC_GETSYMBOL(SYMBOL,TRANSLATION,ERROR)`

Obtains the current translation of a given symbol. If `TRANSLATION` is too short, the translation is truncated without warning or error. `ERROR` is returned if the symbol is undefined only.

`SUBROUTINE SIC_DELSYMBOL(SYMBOL,ERROR)`

Deletes a symbol definition. `ERROR` is returned if the symbol was not defined.

# 3 GreG Programming Manual

This section describes how **GreG** normally used as an interactive plot utility, can also be used as a high level plot library. **GreG** can be used exactly as a standard graphic library, but because of the possibilities of the command line monitor, many other possibilities are accessible.

Before presenting in detail the "Library Version" of **GreG** we should distinguish between three different possible applications of the **GreG** Library :

1. The occasional user who has a single repetitive graphic problem which is part of another complex program. Interactive control is not wanted. This case can often be solved using command procedures and **SIC** images as data format when formatted I/O is definitely too slow. This is very efficient and flexible. If the user already discarded this possibility, he (she) most likely wants the simplest programming ever possible, will be satisfied by standard default values, and is not really worried about optimum efficiency.

2. A programmer wanting to solve a single repetitive graphic problem for use by other people. Interactive action is not wanted. Simple programming is of little importance, but efficiency is a major problem.

3. A programmer wishing to integrate elaborate and flexible graphic applications as part of a more complete data analysis system. Interactive control by the user and error recovery are necessary. Then all **GreG** capabilities are wanted, and in addition this programmer may well be interested to use the possibilities of the **SIC** monitor to "supervise" the data analysis system.

The library version of **GreG** allows all three cases to be solved adequately by offering three different ways to call **GreG** services :

1. Passing a command to **GreG** using the routine `GR_EXEC`
   `GR_EXEC('Command Argument/Option')` will execute the command line exactly as if you had typed it interactively. Instead of `GR_EXEC`, it is recommended to use `GR_EXEC1`, `GR_EXEC2` and `GR_EXECL` for commands of languages GREG1, GREG2 and GTVL respectively.

2. Calling an intermediate formatting routine which generates the appropriate call to `GR_EXEC` from its own arguments. Special entries are used to process possible options. The advantage of this mode is to provide a more standard program interface. Not all commands will be accessible in that way, and it is marginally slower than the previous mode.

3. Calling subroutines which do not correspond to **GreG** commands but directly generates plot actions. This way is the most optimised access, since it bypasses the command line interpretor. However, only standard things can be done like this, and it requires some precautions because of the segmented nature of the graphic library.

All three ways can be used within a single program, and the choice between one or the other is just a matter of convenience and/or efficiency.

In addition, the **GreG** plot library can be used either as a classic package of subroutines ("Library Only"), or as an interactive facility allowing user control at run time by means of the **SIC** monitor possibilities ("Interactive"). The two modes can be mixed in a subroutine, with the important restriction that the "Library Only" mode is just a subset of the "Interactive" mode. It is not possible to change the mode during program execution. A program using **GreG** plot library in "Interactive" mode in fact appears as a superset of the **GreG** interactive utility.

## 3.1 Interaction with FORTRAN programs

For a normal user, it can be said that **GreG** does not interfere at all with a `FORTRAN` program. All interactions with a program concern the system or **SIC** facilities as detailed below.

- I/O Units :
  All logical units used by the **GreG** system and the associated **SIC** monitor are FORTRAN units between 50 and 99. Programs using **SIC** should avoid opening such units, or should get available units through calls to `SIC_GETLUN`.

- Work Space :
  **GreG** uses as much as possible the concept of virtual memory. This means that work space, when required, is allocated dynamically at run time. Hence, **GreG** does not overload a small program. There is currently one exception, the X,Y and Z buffers which have a fixed size allocation of 10000 long-words each. This may change at some time. On large applications, be sure that your virtual memory quota is large enough. Be sure also to run **GreG** in a large enough working set to reduce page faults.

- Special Handler :
  The **SIC** monitor always traps the `^C` action to provide a facility to interrupt procedures at any time. You can bypass this action by adequate programming (see `SIC_CTRLC` routine in the **SIC** manual).

Programmers using **SIC** as command monitor together with **GreG** either in interactive or in library mode, should be aware of the interaction between **GreG** and **SIC** command parsing facility. Each call to `GR_EXEC, GR_EXEC1, GR_EXEC2, GR_EXECL or EXEC_GREG` parses at least one **GreG** command line, and thus modify the pointers accessed by **SIC** argument retrieving routines. Accordingly, any subroutine implementing a user command should retrieve all its arguments **before** calling a **GreG** subroutine.

## 3.2 Basic Routines

1. `LOAD_GREG (Mode)`
   This subroutine must be called before any other reference to **GreG** services. It is used to define the operating mode and to initialize the **GreG** vocabulary into the **SIC** monitor. The argument is of type Character and can be `'LIBRARY'` to initialize **GreG** in the "Library Only" (no interactive **SIC** monitor) mode, or `'INTERACTIVE'` to initialize **GreG** with all **SIC** monitor capabilities. Strings like `'LIBRARY GREG1'` or `'INTERACTIVE GREG2'` can be used to load only one language, although the GREG2\ language requires GREG1\ to function. This routine does not set the **SIC** prompt, neither the Log File which you may specify by calling routine `SIC_OPT`. Please refer to the **SIC** manual.

2. `GR_EXEC(LINE)`
   This is the basic routine for all plot actions. It is able to activate any **GreG** command exactly in the same way as if you had typed it during an interactive session. Use `GR_EXEC` if you do not know to which of the **GreG** languages it pertains, `GR_EXEC1,2 or L` according to the language if you know (and you should). The command line must not include the language field. The command is not written to the **SIC** stack, neither to the Log File.

3. `GR_ERROR()`
   This logical function allows error recovery. It returns the internal error status of **GreG** program, and clears it. If another **GreG** subroutine is called while an error status exist, program execution aborts.

4. `ENTER_GREG` enter **GreG** interactive mode. The user obtains control over **GreG** exactly as if he was running the **GreG** utility. This subroutine can only be used if **GreG** has been initialized in "Interactive" mode.

5. `EXEC_GREG(LINE)`
   execute a command line which can be either a **GreG** command or a **SIC** command (like `'@ PROC'` for example). Control returns to the calling program when the command is completed successfully. If an error occurs, the current **SIC** error recovery action is activated before. This is usually a `PAUSE` which gives interactive control to the user ; control will then return to the calling program only after command `EXIT` (or `^Z`) has been typed. Contrary to `GR_EXEC`, the command is written to the **SIC** stack, and to the Log File. "Interactive" mode is required.

6. PLAY_GREG(LINE)
   execute a **SIC** or **GreG** command and then leave **GreG** in interactive mode. This call is thus more or less equivalent to successive calls to EXEC_GREG and ENTER_GREG (there is a minor difference in case of error). Control returns to the calling program after EXIT. "Interactive" mode is required.

*Only* GR_EXEC *(or its variant) and* GR_ERROR *are allowed in Library Mode.*

## 3.3 Linking

### 3.3.1 UNIX systems

To access **GreG** from your Fortran Program, you need to link to several libraries. All **GreG** libraries are located in $GAG_ROOT/lib where $GAG_ROOT is an environment variable defining where the **GILDAS** software is located. See your local **GILDAS** expert for that.

Then you should use the following link command to link your program

```
f77 -o Program Program.f -L/usr/lib/X11 -L$GAG_ROOT/lib \
-lgdf -lGREG -lcontour -lgtlang -lchar -lsic -limage -lgag -lrary \
-lX11 -lm -lc

where
f77              is the Fortran compiler/linker
Program.f        is your Fortran program.
/usr/lib/X11     indicates where the X11 libraries are located
-lm -lc          are required on some systems
```

On some systems, the **GreG** libraries are shareable, thus avoiding code to be included in your own programs.

### 3.3.2 VMS systems

To access **GreG** from your Fortran Program, you need to link to

```
First library :          GAG_ROOT:[SHARED]GREGLIB/LIB
Second library :         GAG_ROOT:[SHARED]GAGSHARE/LIB
```

The access to these libraries is automatic on some machines. On other sites, issue the command $ SHOW LOGICAL LNK$LIB* to know if automatic linking is enabled. If not enabled, you may either make an explicit reference in the link as :

```
$ LINK PROG1,PROG2,...,-
GAG_ROOT:[SHARED]GREGLIB/LIB,GAGSHARE/LIB
```

or add the following assignments in your LOGIN.COM file for automatic linking to these libraries :

```
$ ASSIGN GAG_ROOT:[SHARED]GREGLIB.OLB LNK$LIBRARY
$ ASSIGN GAG_ROOT:[SHARED]GAGSHARE.OLB  LNK$LIBRARY_1
```

Note however that the GREGLIB library must be specified before the GAGSHARE library in the link command. Be careful if you have other shareable libraries in your link operation to have all these libraries placed as the last ones. As most of the code is shareable, linking to **GreG** is fast and does not produce a large code overhead. Also, you will get the minor updates of **GreG** automatically without need to relink your program.

However you may need to relink your program for major updates. In this case you will receive a message at run-time stating that the version number of the updated shared images (GREGSHR, CHARSHR, CONSHR, GTVSHR, IMASHR, GAGSHR or SICSHR) no longer matches the version number at link-time and you will not be able to run your program without relinking it. If this happens to you, please consult the latest description of the **GreG** manual to see whether any calling sequence might have been modified. If not, linking again will be sufficient.

## 3.4 Running

If you are using **GreG** in "Library Only" mode, you can just run your program normally.

If you are using the "Interactive" mode you need to provide the assignments of **GreG** help files and working files to your program. All compulsory assignments are made system wide, so you can just run the program. You will obtain help for the **SIC** command monitor and the log file will be written on the logical unit `LOG`, (unless you call `SIC_OPT`, see the **SIC** manual). If you have not assigned the logical name `LOG` to a file name, each run of your program will create a new version of the file `LOG.DAT` in your current directory. No automatic purge of the log file will be made when your program exits.

## 3.5 Example

A simple and typical example is available in the Fortran file `GAG_UTIL:GREGTEST.FOR`. Just print it. If it is close to your application, you may copy it into your directory and adapt it to your wishes.

## 3.6 Array Transfer

Subroutines with data arrays transferred to or obtained from **GreG** have a Real*4 and a Real*8 version. The simple precision has a name beginning by `GR4_`, the double precision a name beginning by `GR8_`. In the argument list description, `REAL` will mean Real*4 for the `GR4_` version, Real*8 for the `GR8_`. These routine work by copying the data. For really big arrays, it is more efficient to transfer the information by reference, though SIC variables (see the SIC manual).

### 3.6.1 GR4_GIVE - GR8_GIVE

`GR4_GIVE(NAME,NXY,ARRAY)`

This subroutine passes One-Dimensional array `ARRAY` to **GreG** as the X, Y, or Z array according to the given `NAME`. It is the optimal way to initialize the One-Dimensional arrays of **GreG** with the data you have computed within your application program.

```
NAME    is CHARACTER*1 and may be X, Y or Z
NXY     is the number of values set in ARRAY
ARRAY   is a REAL array of size NXY.
```

### 3.6.2 GR4_GET - GR8_GET

`GR4_GET(NAME,NXY,ARRAY)`

This subroutine is the reverse of the `GR4(8)_GIVE` routines. It passes One-Dimensional array `ARRAY` from **GreG** to your program as the X, Y, or Z array according to the given `NAME`. It allows to benefit in your program of the flexible input formats of **GreG** .

```
NAME    is CHARACTER*1 and may be X, Y or Z     Input
NXY     dimension of ARRAY                      Input
        number of values returned in ARRAY      Output
ARRAY   is a REAL array of size NXY             Output
```

### 3.6.3 GR4_RGIVE - GR8_RGIVE

`GR4_RGIVE(NX,NY,CONV,R)`

This subroutine passes a two-Dimensional array to **GreG** as the Regular Grid array used for mapping.

```
NX,NY   Integers, array dimensions
CONV    Real*8 array of dimension 6
        It contains respectively
        CONV(1) Reference pixel in X (First dimension of R)
        CONV(2) X User coordinate value at CONV(1)
        CONV(3) X User coordinate increment per pixel (may be negative)
```

```
                CONV(4)-CONV(6) same as above for Y (Second dimension of R)
        R       REAL   array (NX,NY) to be transferred.
```

If R is Real*4, the array is not physically copied but its address is computed by **GreG** for later use. **GreG** will not modify anything in it. If of type Real*8, virtual memory is allocated to create a Real*4 array of same dimensions.

### 3.6.4 GR4_LEVELS - GR8_LEVELS

`GR4_LEVELS(NL,LEVELS)`

This subroutine initializes a set of contour levels for mapping by **GreG** . `LEVELS` is a `REAL` array of dimension `NL`.

## 3.7 Immediate Routines

The following routines do not use the **SIC** command line interpretor. They are essentially internal **GreG** routines made available to the user, and are thus very efficient to use. As above, they have a Real*4 and a Real*8 version.

For optimization purposes, these routines do not include any explicit segmentation of the plot. In order to be consistent with the philosophy of the interactions between **GreG** and the `GTVIRT` graphic library, you must enclose a set of calls to the immediate routines between a call to `GR_SEGM` and `GR_OUT`. Ex:

```
CALL GR_SEGM('Nom',ERROR)  ! Close current graphic segment and open
                           ! a new one
CALL GR4_CONNECT (...)     ! Fill this segment with plot coordinates
CALL GR4_MARKER (...)      ! etc..
CALL GR_OUT                ! Make the segment visible on screen
```

### 3.7.1 GR_SEGM

`GR_SEGM(NAME,ERROR`

Close the current graphic segment and open a new graphic segment with the current plotting attributes selected by `PENCIL`. All the commands of **GreG** open at least one new segment, but the immediate routines do not. This routine must be called prior to calling a series of immediate routines to ensure that the plot will appear with the currently selected graphic attributes, and to allow a selective erasure of the plot. NAME is a character string indicating the desired name of the segment, and ERROR a logical error flag. All plot request issued between two successive calls to `GR_SEGM` will make a single graphic segment. Note however that every **GreG** command having an effective plot action creates one or more graphic segments.

### 3.7.2 GR_OUT

`GR_OUT`

Updates the graphic output. This routine must be called when you wish to make visible a series of calls to the immediate routines.

### 3.7.3 DRAW - RELOCATE

`DRAW(XU,YU) RELOCATE(XU,YU)`

Basic pen down or up movement in User coordinates (Real*8 values). There is no Real*4 version.

### 3.7.4 GDRAW - GRELOCATE

`GDRAW(X4,Y4) GRELOCATE(X4,Y4)`

Basic pen down or up movement in Physical coordinates (Real*4 values). There is no Real*8 version.

### 3.7.5 GR4_PHYS_USER - GR8_PHYS_USER

GR4_PHYS_USER (XP,YP,XU,YU,NXY)

Convert Physical coordinates (XP,YP always Real*4 values) to User coordinates (XU,YU, REAL values). NXY is the number of values.

### 3.7.6 GR4_USER_PHYS - GR8_USER_PHYS

GR4_USER_PHYS(XU,YU,XP,YP,NXY)

Convert User coordinates (XU,YU, REAL values) to Physical coordinates (XP,YP, always Real*4 values). NXY is the number of values.

### 3.7.7 GR4_CONNECT - GR8_CONNECT

GR4_CONNECT(NXY,X,Y,BVAL,EVAL)

This subroutine connects all data points represented by the X and Y arrays passed in arguments. BVAL and EVAL are used for blanked values. EVAL negative means no blanking.

```
Arguments :
        NXY     INTEGER         Input
        X       REAL (NXY)      Input
        Y       REAL (NXY)      Input
        BVAL    REAL            Input
        EVAL    REAL            Input
```

### 3.7.8 GR4_HISTO - GR8_HISTO

GR4_HISTO(NXY,X,Y,BVAL,EVAL)

```
Arguments :
        NXY     INTEGER         Input
        X       REAL (NXY)      Input
        Y       REAL (NXY)      Input
        BVAL    REAL            Input
        EVAL    REAL            Input
```

### 3.7.9 GR4_MARKER - GR8_MARKER

GR4_MARKER(NXY,X,Y,BVAL,EVAL)

Markers of current size are plotted at each data point.

```
Arguments :
        NXY     INTEGER         Input
        X       REAL (NXY)      Input
        Y       REAL (NXY)      Input
        BVAL    REAL            Input
        EVAL    REAL            Input
```

### 3.7.10 GR4_CURVE - GR8_CURVE

GR4_CURVE(NXY,X,Y,Z,VAR,PER,BVAL,EVAL,ERROR)

Plots a smooth curve from the (X,Y) values using the requested interpolant. Z is either a dummy argument or a parameter for the curve representation depending on the VAR value. VAR indicates which is the variable to use for interpolation. PER indicates whether the curve is periodic or not. BVAL and EVAL define the blanking value and the blanking tolerance (set EVAL negative to disable blanking checking). ERROR is an error flag set if the curve could not be produced. The current accuracy is used for the interpolation.

```
Arguments :
        NXY     INTEGER         Input
        X       REAL (NXY)      Input
        Y       REAL (NXY)      Input
        VAR     CHARACTER*(*)   Input
        PER     LOGICAL         Input
        BVAL    REAL            Input
        EVAL    REAL            Input
        ERROR   LOGICAL         Output
```

### 3.7.11 GR4_EXTREMA - GR8_EXTREMA

`GR4_EXTREMA(NXY,X,BVAL,EVAL,XMIN,XMAX,NMIN,NMAX)`

Compute the extrema of the input array avoiding blanked values.

```
Arguments :
        NXY     INTEGER         Input   Number of points
        X       REAL (NXY)      Input   Array
        BVAL    REAL            Input   Blanking value
        EVAL    REAL            Input   Tolerance on blanking
        XMIN    REAL            Output  Minimum value
        XMAX    REAL            Output  Maximum value
        NMIN    INTEGER         Output  Pixel of the minimum X(NMIN) = XMIN
        NMAX    INTEGER         Output  Pixel of the maximum
```

### 3.7.12 GR8_BLANKING

`GR8_BLANKING(BVAL,EVAL)`

Define the blanking value to be used later. It is equivalent to call `GR_EXEC('SET BLANKING BVAL EVAL')`, but the later form requires formatting of values.

```
Arguments :
        BVAL    REAL            Input   Blanking value
        EVAL    REAL            Input   Blanking precision
```

### 3.7.13 GR8_SYSTEM - GR8_PROJEC

`GR8_SYSTEM (ICODE)`
`GR8_PROJEC (X,Y,A,ICODE)`

Define respectively the coordinate projection system and the projection constants. The `SYSTEM` code can be 1 for `UNKNOWN`, 2 for `EQUATORIAL (1950.0)`, 3 for `GALACTIC`. The projection code is 0 for `NONE`, 1 for `GNOMONIC`, 2 for `ORTHOGRAPHIC`, 3 for `AZIMUTHAL`, 4 for `STEREOGRAPHIC`, 5 for `LAMBERT` cylindrical, 6 for `AITOFF` equal area and 7 for `RADIO` (also known as global SINUSOIDAL) projection.

```
Arguments :
        ICODE   INTEGER         Input
        X       REAL            Input       Projection center
        Y       REAL            Input       Projection center
        A       REAL            Input       Projection Angle
```

### 3.7.14 GR4_RVAL

`GR4_RVAL(XU,YU,Z4)`

Returns a map value at a given point in user coordinates.

```
Arguments :
        XU      REAL*8          Input
        YU      REAL*8          Input
        Z4      REAL*4          Output
```

### 3.7.15 GR_WHERE

`GR_WHERE(XU,YU,X4,Y4)`
Returns the pen position with the same conventions as `GR_CURS`

```
Arguments :
        XU      R*8     X User coordinates          Output
        YU      R*8     Y User coordinates          Output
        X4      R*4     X Plot coordinates          Output
        Y4      R*4     Y Plot coordinates          Output
```

### 3.7.16 GR8_TRI

`GR8_TRI(X,INDEX,N,*)`
Sorting program that uses a quicksort algorithm. Applies for an input array of Real*8 values which is reordered. It also returns an array of indexes sorted for increasing order of X. You can use `GR8_SORT` to reorder other arrays associated with X.

```
Arguments :
        X       R*8(*)  Unsorted/Sorted array           Input/Output
        INDEX   I(*)    Integer array of sorted indexes Output
        N       I       Length of arrays                Input
        *       Label   Error return
```

### 3.7.17 GR8_SORT

`GR8_SORT(X,XSORT,INDEX,N)`
Reorder a real*8 array using the sort indexes computed by `GR8_TRI`. Note that `X` and `XSORT` must be different (i.e. sorting cannot take place within the same array).

```
Arguments :
        X       R*8(*)  Unsorted/Sorted array           Input/Output
        XSORT   R*8(*)  Sorted array                    Work space
        INDEX   I(*)    Integer array of sorted indexes Input
                        (obtained by GR8_TRI)
        N       I       Length of arrays                Input
```

### 3.7.18 GR_CLIP

`LOGICAL FUNCTION GR_CLIP(clip)`
Turn on `(CLIP = .TRUE.)` or off `(CLIP = .FALSE.)` clipping of lines, and return current status in `GR_CLIP`. By default, clipping is on. Caution : some **GreG** subroutines force clipping off and reset it on upon exit.

## 3.8 The cursor routine

`GR_CURS (XU,YU,X4,Y4,CODE)`
Calls the interactive graphic cursor and returns its position when you hit any alphanumeric key on the keyboard.

```
Arguments :
        XU      REAL*8       X User coordinates    Output
        YU      REAL*8       Y User coordinates    Output
        X4      REAL*4       X Plot coordinates    Output
        Y4      REAL*4       Y Plot coordinates    Output
        CODE    CHARACTER*1  Character struck      Output
```

The subroutine returns `CODE = 'E'` when an error occurs.

For X-Window terminals, button 1 returns ^ , 2 returns & and 3 returns *.

## 3.9 GreG High-Level Subroutines

These routines essentially format the command line to pass it later to the `GR_EXEC` subroutine, and are thus the less efficient routines of the **GreG** library. They are provided essentially for user convenience because the formatting needed to use `GR_EXEC` might be tedious. Note all **GreG** commands have the high level equivalent, but all can be used with `GR_EXEC`.

Each subroutine corresponds to a command, and each entry corresponds to an option of that command. The subroutine and entry names are built from the 4 first characters of the corresponding command and option names. The entries must be called before the subroutine, since it is this one which effectively transmit the command to `GR_EXEC`.

The conventional type of arguments are

```
NAME            Character
ARG,ARG1,...    Real*8
IARG,IARG1,...  Integer*4
NARG            Integer*4
```

When `NARG` is present, all arguments need not be passed : trailing arguments may be omitted. `NARG` is used to give the actual number of arguments passed after `NARG` itself and it must be set precisely. All arguments before `NARG`, usually the character string `NAME`, and the argument `NARG` must always be present (even if `NAME=' '`). Note that if `ARG1` is missing, `ARG2` cannot be present. Note also that the double quotes should not be passed for character strings. For instance, the interactive command `LABEL ''A little toy''` should be replaced by `CALL GR_LABE('A little toy')`.

Example : `CALL GR_DRAW ('MARKER', 2, 0.3D0, 0.8D0)`

Note that the `ARG1` and `ARG2` arguments are here expressed as constants, and the D exponent is required as they must be Real*8 values.

The high level routines are not yet fully guaranteed as up to date. In the following description, each high level subroutine is preceeded by the assumed syntax for the equivalent command. If this syntax differs from the current internal help description, using the discrepant parts of the high level routine will cause a fatal error, but common parts of the syntax can be used safely.

For the GTVL language, the following routines are available

```
CLEAR [Argument]
        SUBROUTINE GR_CLEA(NAME)

DEVICE [Type [Descriptor]] [/OUTPUT Logical_Name]
        SUBROUTINE GR_DEVI(NAME)
        All arguments of command DEVICE being character strings, it is
        easy to concatenate them into NAME.
```

For the GREG1 language, the routines are

```
AXIS Name [A1 A2] [/LOCATION X Y] [/TICK Orientation [BIG SMALL]]
        [/LABEL Position] [/[NO]LOG] [/ABSOLUTE]
        SUBROUTINE GR_AXIS(NAME,NARG,ARG1,ARG2)         ! 28-Sep-1986
```

```
        ENTRY GR_AXIS_LOCA(NARG,ARG1,ARG2)
        ENTRY GR_AXIS_TICK(NAME,NARG,ARG1,ARG2)
        ENTRY GR_AXIS_LABE(NAME)
        ENTRY GR_AXIS_LOG
        ENTRY GR_AXIS_NOLO
        ENTRY GR_AXIS_ABSO

BOX [Arguments]
        SUBROUTINE GR_BOX(NAME)                          ! 28-Sep-1986
        ENTRY GR_BOX_ABSO

COLUMN [X Nx] [Y Ny] [E Ne] [/FILE File] [/LINES Lmin [Lmax]]
        [/TABLE TableName]
        SUBROUTINE GR_COLU(NAME)                         ! 28-Sep-1986
        As this routine is normally of no use in the library version,
        it requires you to code explicitly the remaining part of the
        command line. Hence, it should be equivalent to use
        either GR_EXEC('GREG1\COLUMN '//NAME)
        or GR_EXEC1('COLUMN '//NAME)

CONNECT [/BLANKING Bval Eval]                            ! 28-Sep-1986
        SUBROUTINE GR_CONN
        ENTRY GR_CONN_BLAN(NARG,ARG1,ARG2)

DRAW [Action [X Y]] [/USER] [/BOX N] [/CHARACTER N] [/CLIP]
        SUBROUTINE GR_DRAW(NAME,NARG,ARG1,ARG2)
        ENTRY GR_DRAW_CHAR(NARG,IARG)
        ENTRY GR_DRAW_USER
        ENTRY GR_DRAW_BOX(NARG,IARG)
        ENTRY GR_DRAW_CLIP

        Note that no support is given for DRAW TEXT and DRAW FILL_AREA,
        unless you specify in NAME all the arguments and set NARG to 0.
        DRAW TEXT can easily be replaced by GR_DRAW('RELOCATE'...)
        followed by a call to GR_LABE.

ERRORBAR NAME
        SUBROUTINE GR_ERRO(NAME)                         ! 28-Sep-1986

HISTOGRAM [/BASE [Ybase]] [/BLANKING Bval Eval]
        SUBROUTINE GR_HIST                               ! 28-Sep-1986
        ENTRY GR_HIST_BASE(ARG)
        ENTRY GR_HIST_BLAN(NARG,ARG1,ARG2)

LABEL "String" [/X] [/Y] [CENTERING N] [/APPEND]
        SUBROUTINE GR_LABE(NAME)                         ! 28-Sep-1986
        ENTRY GR_LABE_X
        ENTRY GR_LABE_Y
        ENTRY GR_LABE_CENT(IARG)
        ENTRY GR_LABE_APPE

LIMITS [Xmin Xmax Ymin Ymax] [/XLOG] [/YLOG] [/RGDATA] [/REVERSE [X] [Y]]
        [/BLANKING Bval Eval]
        SUBROUTINE GR_LIMI(NARG,ARG1,ARG2,ARG3,ARG4)     ! 28-Sep-1986
```

```
        ENTRY GR_LIMI_XLOG
        ENTRY GR_LIMI_YLOG
        ENTRY GR_LIMI_RGDA
        ENTRY GR_LIMI_REVE(NAME)
        ENTRY GR_LIMI_BLAN(NARG,ARG1,ARG2)
        Arguments of GR_LIMI can be omitted with the standard VAX
        convention to indicate that automatic limit must be computed
        for this one. For example
                CALL GR_LIMI_XLOG
                CALL GR_LIMI(4,0.d0, ,-10.d0,10.d0)
        is equivalent to
                CALL GR_EXEC1('LIMITS 0 * -10 10/XLOG')
        Presently, there is no support for the fifth argument (Angular
        unit or Absolute coordinates) and for the =, < and > possibilities
        of command LIMITS in this High Level routine. To use these
        possibilities, you should use directly GR_EXEC1('LIMITS ...').

PENCIL [N] [/COLOUR C] [/DASHED D] [/WEIGHT W] [/DEFAULT]
        SUBROUTINE GR_PEN(NARG,IARG)                    ! 28-Sep-1986
        ENTRY GR_PEN_DASH(IARG)
        ENTRY GR_PEN_WEIG(IARG)
        ENTRY GR_PEN_COLO(IARG)
        ENTRY GR_PEN_DEFA

POINTS [Size] [/BLANKING Bval Eval]
        SUBROUTINE GR_POIN(NARG,ARG1)
        SUBROUTINE GR_POIN_BLAN(NARG,ARG1,ARG2)

RULE [X] [Y] [/MAJOR [/MINOR]
        SUBROUTINE GR_RULE(NAME)                        ! 28-Sep-1986
        ENTRY GR_RULE_MAJO
        ENTRY GR_RULE_MINO

SET Something [Value1 [Value2]...]]]
        SUBROUTINE GR_SET(NAME,NARG,ARG1,ARG2,ARG3,ARG4) ! 28-Sep-1986

SHOW
        SUBROUTINE GR_SHOW(NAME)                        ! 28-Sep-1986

TICKSPACE SmallX BigX SmallY BigY                       ! 28-Sep-1986
        SUBROUTINE GR_TICK(NARG,ARG1,ARG2,ARG3,ARG4)
```

The following commands correspond to the GREG2\ Language.

```
EXTREMA [/BLANKING Bval Eval] [/PLOT]
        SUBROUTINE GR_EXTR                              ! 28-Sep-1986
        ENTRY GR_EXTR_BLAN(NARG,ARG1,ARG2)
        ENTRY GR_EXTR_PLOT

LEVELS List
        SUBROUTINE GR_LEVE(NAME)
        Coding the list in the required format may be funny.
        Use GR4_LEVELS or GR8_LEVELS instead, they are more convenient.
```

```
RGDATA File_Name [/SUBSET IX1 IY1 IX2 IY2]
        SUBROUTINE GR_RGDA(NAME)                          ! 28-Sep-1986
        ENTRY GR_RGDA_SUBS(NARG,IARG1,IARG2,IARG3,IARG4)

RGMAP [/ABSOLUTE Value] [/PERCENT Value] [/KEEP] [/BLANKING Bval Eval]
        [/GREY Colour Ntry] [/PENS Pos Neg]
        SUBROUTINE GR_RGMA                                ! 28-Sep-1986
        ENTRY GR_RGMA_ABSO(ARG)
        ENTRY GR_RGMA_PERC(ARG)
        ENTRY GR_RGMA_BLAN(NARG,ARG1,ARG2)
        ENTRY GR_RGMA_KEEP
        ENTRY GR_RGMA_PENS(NARG,IARG1,IARG2)
        No support is yet given for option /GREY because it is still
        rather experimental.
```

Remember that if anything available in interactive seems to be missing in the previous list, you can always use GR_EXEC to access it.

# 4 Task Programming Manual

## 4.1 General Outline and Data Structure of Images

The **GILDAS** software is designed to work in an heterogeneous network, where each computer may have its own floating point and integer number representation and its own operating system. Images created on any computer should be accessible transparently from any other computer in the network.

To allow such a portability and yet preserve efficiency when working on a single type of machines, all files are written in the binary representation of the machine on which they were created. A library of subroutines is used to access the images and perform the necessary format conversion between the different representations of real and integer numbers. So far, 3 representations are recognised: VAX format, IEEE format (DEC DS Workstation) and EEEI format (Sun SparcStation, IBM RS-6000 series, etc...).

The images have the following organisation :

- Images are basically direct access files with a blocksize of 512 bytes. This correspond to the system block size on VAX-VMS machines.
- The first block is a header block, defining the size of the image and all major parameters, such as World Coordinate System definition.
- The following blocks containing the image array itself.
- There may be trailing blocks for additional information. These trailing blocks are not compulsory, and may be ignored by the processing software.

The header starts with 'GILDAS', followed by one character which indicates the type of integer and floating point number representation

- Underscore "_" for VAX machines
- Dot "." for swapped IEEE machines (IBM RS-6000, SUN Sparc, etc...)
- Minus "-" for non-swapped IEEE machines (DEC DS series)

and extra text indicating the type of information in the image:

- `IMAGE` for all images (up to 4-D arrays)
- `UVDAT` for tables of unsorted, unprecessed UV data
- `UVSOR` for tables of sorted, precessed UV data

On computers which support such possibilities (VMS systems), **GILDAS** makes extensive use of memory mapping to access the images : instead of being read into memory through standard I/O techniques, the disk file containing an image is directly made part of the virtual memory accessed by the program, through the use of the appropriate system routines. Physical I/O between this virtual memory and the physical memory is then later handled by the system memory management.

On other computers, the image is copied into memory using standard FORTRAN direct I/O. Provided adequate programmation by the application programmer, only the necessary part of the image is read or mapped. This is a totally transparent process for the application programmer, who will always consider the image as a FORTRAN array in virtual memory.

The portable version of the **GILDAS** software makes the distinction between an image and the "incarnation" of an image subset in memory. Each image has an associated "Image Slot" (IS), while each memory part has an associated "Memory Slot" (MS). Several memory slots may corresponds to several "windows" into a single image slot.

To read a file requires six basic steps:

- allocation of an *Image Slot* using `GDF_GEIS`.
- connection of an image to the slot using `GDF_REIS` or `GDF_WRIS`.

- reading the header using GDF_RHSEC
- connection of a *Memory Slot* to the image (or a subset of it) using GDF_GEMS
- once the *Memory Slot* is no longer needed, disconnection using GDF_FRMS
- once the image slot is no longer required, disconnection using GDF_FRIS

Creation of a new file is slightly different:

- allocation of an *Image Slot* using GDF_GEIS
- preparatin of the header using e.g. GDF_WHSEC
- creation of the image to the slot using GDF_CRIS. The header is written at this stage.
- connection to the image (or a subset of it) using GDF_GEMS
- once the *Memory Slot* is no longer needed, disconnection using GDF_FRMS. This is the step which actually does the writing.
- once the image slot is no longer required, disconnection using GDF_FRIS

## 4.2 Image Slot Handling

```
SUBROUTINE GDF_GEIS (IS,ERROR)
```

```
      GDF  GEt Image Slot
           IS      I       Slot number                    Output
           ERROR   L       Error flag                     Output
```

GDF_GEIS returns a unique image slot number IS, for further use in all other GDF_xxxx routines.

```
SUBROUTINE GDF_CLIS (IS,ERROR)
```

```
      GDF  CLose Image Slot
           IS      I       Slot number                    Input
           ERROR   L       Error flag                     Output
```

GDF_CLIS close an image slot IS, disconnecting all associated memory slot after flushing all pending updates on the image. The image slot IS stays reserved, but available for further use.

```
SUBROUTINE GDF_FRIS (IS,ERROR)
```

```
      GDF  FRee Image Slot
           IS      I       Slot number                    Input
           ERROR   L       Error flag                     Output
```

GDF_CLIS free an image slot IS, disconnecting all associated memory slot after flushing all pending updates on the image. The image slot IS should no longer be referenced in any call after this operation.

```
INTEGER FUNCTION GDF_STIS(IS)
```

```
      GDF  STatus of Image Slot
           IS      I       Slot number                    Input
```

Return status of slot: -1 No such slot, 0 Empty (Not allocated), 1 Read (Opened for ReadOnly), 2 Full (Allocated but not opened), 3 Write (Opened for ReadWrite).

## 4.3 Image Connection

Once a slot is reserved, it must be associated with an image. The following 4 routines connect an image to a specified image slot IS, in one of the 4 possible access modes (CReate, EXtend, REad only, Write and Read). No part of the image is immediately accessible after that, but the image slot is ready for memory connection using GDF_GEMS.

```
SUBROUTINE GDF_CRIS (IS,GTYPE,NAME,FORM,SIZE,ERROR)


      GDF  CReate Image Slot
      Arguments:
           IS      I       Slot number                    Input
           GTYPE   C*(*)   Image type                     Input
           NAME    C*(*)   File name                      Input
           FORM    I       Image format (Real,Integer...) Input
           SIZE    I       Image size                     Input
           ERROR   L       Error flag                     Output
```

Creates a new file from the information available in image slot IS. The internal header should have been defined (through calls to GDF_WHSEC) before, and is written on the new file header.

```
SUBROUTINE GDF_EXIS (IS,GTYPE,NAME,FORM,SIZE,ERROR)


      GDF  EXtend Image Slot
      Arguments:
           IS      I       Slot number                    Input
           GTYPE   C*(*)   Image type                     Input
           NAME    C*(*)   File name                      Input
           FORM    I       Image format (Real,Integer...) Input
           SIZE    I       Image size                     Input
           ERROR   L       Error flag                     Output
```

This routine is used to change the size of an image, usually by increasing the last dimension of the image. The new internal header must have been defined before in image slot IS, by use of the GDF_WHSEC routine.

```
SUBROUTINE GDF_REIS (IS,GTYPE,NAME,FORM,SIZE,ERROR)


      GDF  REad Image Slot
      Arguments:
           IS      I       Slot number                    Input
           GTYPE   C*(*)   Image type                     Output
           NAME    C*(*)   File name                      Input
           FORM    I       Image format (Real,Integer...) Output
           SIZE    I       Image size                     Output
           ERROR   L       Error flag                     Output
```

This routine is used to open an existing image for ReadOnly operations. The image is available for file sharing.

```
SUBROUTINE GDF_WRIS (IS,GTYPE,NAME,FORM,SIZE,ERROR)
```

```
GDF  WRite Image Slot
Arguments:
     IS      I       Slot number                     Input
     GTYPE   C*(*)   Image type                      Output
     NAME    C*(*)   File name                       Input
     FORM    I       Image format (Real,Integer...)  Output
     SIZE    I       Image size                      Output
     ERROR   L       Error flag                      Output
```

This routine is used to open an existing image for ReadWrite operations. The image is not available for file sharing.

## 4.4 Memory Connection

After an image is connected, a part of it should be brought into virtual memory. The access type for this virtual memory area (ReadOnly or ReadWrite) depends on the type of image connection.

```
      SUBROUTINE GDF_GEMS (MS, IS, BLC, TRC, ADDR, FORM, ERROR)
-----------------------------------------------------------------------
 GDF  Get Memory Slot
      MS      I       Memory Slot number              Output
      IS      I       Image Slot number               Input
      BLC     I(4)    Bottom Left Corner              Input
      TRC     I(4)    Top Right Corner                Input
      ADDR    I       Virtual memory address          Output
      FORM    I       Type of data                    Input
      ERROR   L       Logical error flag              Output
-----------------------------------------------------------------------
```

GDF_GEMS reads a subset of the image connected to slot IS into a memory area (memory slot MS) located at address ADDR. The image subset is "incarnated" into the specified data type FORM, which may be different from the image data type. When BLC(i) and TRC(i) are set to zero, they default to the current image dimension (i.e BLC(i)=1 and TRC(i)=Dim(i)). After this routine, virtual memory address ADDR is the start of an array of type FORM containing an incarnation of the image subset that can be used for further processing.

```
      SUBROUTINE GDF_FRMS (MS,ERROR)
-----------------------------------------------------------------------
 GDF  FRee Memory Slot
-----------------------------------------------------------------------
```

GDF_FRMS Frees the memory slot MS. If the connected image was connected with write access, the image is updated. The memory slot is no longer available after this operation.

```
      SUBROUTINE GDF_UPMS (MS,ERROR)
-----------------------------------------------------------------------
 GDF  UPdate Memory Slot
-----------------------------------------------------------------------
```

GDF_UPMS Updates the image connected to the memory slot MS. The memory slot is left unmodified. This routine is provided for safety measures.

The I/O (or mapping) are thus only done in the GDF_xxMS routines, in a system dependent way. All data format translation (incarnation in a different type, or machine dependent data types) are done at this level. This allows a transparent operation in an heterogeneous environment.

## 4.5 Image Header Access

### 4.5.1 Outline

Each image slot has an associated buffer area, from which header information can be retrieved. This buffer, named HEADER(*,IS) for slot IS, is an array of size is 128 words, containing an copy of the file header, but converted to the machine-dependent number format. Subroutines are available to read (or write) the header section from (to) these internal buffers: `GDF_RHSEC` and `GDF_WHSEC`.

To provide pre-defined data structures with the appropriate header item type, 3 named commons called X, Y or Z are described in include files `INC:xPAR.INC`, where "x" is the common "name". Routines are available to copy headers from one common to another (`GDF_CHxy`), and to read header from (or copy header to) the internal array HEADER (`GDF_READx, GDF_WRITx`).

Each named common contains a variable to define one memory slot, `x_MSLO`, but more memory slots can be used simultaneously by declaring other variables in the application program.

### 4.5.2 Named Common Description

The named commons have the following structure, given here for X common. Replace X by Y or Z respectively for the others. Note that each named common is in fact made of 3 different FORTRAN commons, to handle different types of information. Two representations of the character strings exist, one in XCPAR as character variables, one in XPAR as integer arrays. The application program should deal only with the XCPAR representation.

```
        INTEGER MXCPAR,MXIPAR,MXPAR
        PARAMETER (MXPAR=128)      ! 128 header integers
        PARAMETER (MXIPAR=5)       ! 5 Extra integers
        PARAMETER (MXCPAR=9)       ! 9 character*12 strings
        CHARACTER*120 X_FILE       ! File name
        CHARACTER*12 X_TYPE        ! Image type
        CHARACTER*12 X_UNIT        ! Image unit
        CHARACTER*12 X_CODE(4)     !        Axis type
        CHARACTER*12 X_SYST        ! System type
        CHARACTER*12 X_NAME        ! Source name
        CHARACTER*12 X_LINE        ! Line name
        COMMON /XCPAR/ X_FILE,
    +        X_TYPE,X_UNIT,X_CODE,X_SYST,X_NAME,X_LINE
        INTEGER X_SIZE             ! image size
        INTEGER X_ADDR             ! start map address
        INTEGER X_ISLO             ! Image slot
        INTEGER X_MSLO             ! Memory Slot
        LOGICAL X_READ             ! Read Only status
        COMMON /XIPAR/ X_SIZE,X_ADDR,X_ISLO,X_MSLO,X_READ
        INTEGER X_BUFF(MXPAR)
        REAL*8 X_CONV(3,4)
        EQUIVALENCE (X_CONV(1,1),X_REF1)
        EQUIVALENCE (X_ITYP,X_BUFF)
*
* /XPAR/
        INTEGER X_ityp(3)    ! Image Type TYPE
        INTEGER*4 X_form     ! Image Format FORM
        INTEGER*4 X_nvb      ! Number of blocks of image
        INTEGER*4 X_fill(5)  ! Reserved space
*
        INTEGER X_GENE       ! Size of GENEral section
        INTEGER X_NDIM       ! Number of dimensions
```

```
      INTEGER X_DIM(4)     ! Dimensions
      REAL*8 X_REF1        ! Reference Pixel for First Axis
      REAL*8 X_VAL1        ! Value at Reference Pixel
      REAL*8 X_INC1        ! Increment per Pixel
      REAL*8 X_REF2        ! As above for Second Axis
      REAL*8 X_VAL2
      REAL*8 X_INC2
      REAL*8 X_REF3
      REAL*8 X_VAL3
      REAL*8 X_INC3
      REAL*8 X_REF4
      REAL*8 X_VAL4
      REAL*8 X_INC4
*
      INTEGER X_BLAN       ! Length of Blanking Section
      REAL X_BVAL          ! Blanking Value
      REAL X_EVAL          ! Tolerance on Blanking
*
      INTEGER X_EXTR       ! Length of Extrema Section
      REAL X_RMIN          ! Minimum
      REAL X_RMAX          ! Maximum
      INTEGER X_MIN1       ! Pixel of Minimum (first axis)
      INTEGER X_MAX1       !   "   of Maximum
      INTEGER X_MIN2       !   "    " Minimum (second axis)
      INTEGER X_MAX2
      INTEGER X_MIN3
      INTEGER X_MAX3
      INTEGER X_MIN4
      INTEGER X_MAX4
*
      INTEGER X_DESC       ! Description section
      INTEGER X_IUNI(3)    ! Unit Name X_UNIT
      INTEGER X_ICOD(3,4)  ! Axis Name X_CODE(4)
      INTEGER X_ISYS(3)    ! Coordinate System X_SYST
*
      INTEGER X_POSI       ! Position section
      INTEGER X_ISOU(3)    ! Source Name X_SOUR
      REAL*8 X_RA          ! Right Ascension (Radians)
      REAL*8 X_DEC         ! Declination (Radians)
      REAL*8 X_LII         ! Galactic Longitude (Radians)
      REAL*8 X_BII         ! Galactic Latitude (Radians)
      REAL*4 X_EPOC        ! Epoch of RA and DEC (Years)
*
      INTEGER X_PROJ       ! Projection Section
      INTEGER X_PTYP       ! Projection Type
      REAL*8 X_A0          ! Longitude of Projection Center
      REAL*8 X_D0          ! Latitude of Center (Radians)
      REAL*8 X_PANG        ! Position Angle
      INTEGER X_XAXI       ! First Projected axis
      INTEGER X_YAXI       ! Second Projected axis
*
      INTEGER X_SPEC       ! Spectroscopy Section
      INTEGER X_ILIN(3)    ! Line name X_LINE
      REAL*8 X_FRES        ! Frequency Resolution (MHz)
```

```
      REAL*8 X_FIMA        ! Image Frequency (MHz)
      REAL*8 X_FREQ        ! Rest Frequency (MHz)
      REAL*4 X_VRES        ! Velocity resolution (km/s)
      REAL*4 X_VOFF        ! Velocity Offset (km/s)
      INTEGER X_FAXI       ! Frequency axis (MHz)
*
      INTEGER X_RESO       ! Resolution Section
      REAL*4 X_MAJO        ! Major Axis (User Units)
      REAL*4 X_MINO        ! Minor Axis (User Units)
      REAL*4 X_POSA        ! Position Angle (Radians)
      COMMON /XPAR/X_ITYP,X_FORM,X_NVB,X_FILL,X_GENE,X_NDIM,X_DIM,
     +    X_REF1,X_VAL1,X_INC1,X_REF2,X_VAL2,X_INC2,X_REF3,X_VAL3,
     +    X_INC3,X_REF4,X_VAL4,X_INC4,X_BLAN,X_BVAL,X_EVAL,X_EXTR,
     +    X_RMIN,X_RMAX,X_MIN1,X_MAX1,X_MIN2,X_MAX2,X_MIN3,X_MAX3,
     +    X_MIN4,X_MAX4,X_DESC,X_IUNI,X_ICOD,X_ISYS,X_POSI,X_ISOU,
     +    X_RA,X_DEC,X_LII,X_BII,X_EPOC,X_PROJ,X_PTYP,X_AO,X_DO,
     +    X_PANG,X_XAXI,X_YAXI,X_SPEC,X_ILIN,X_FRES,X_FIMA,X_FREQ,
     +    X_VRES,X_VOFF,X_FAXI,X_RESO,X_MAJO,X_MINO,X_POSA
```

## 4.6 Basic Header Handling

```
      SUBROUTINE GDF_UPIH (IS,NAME,ERROR)
-----------------------------------------------------------------------
 GDF  UPdate Image Header
      Update an image header
 Arguments :
      IS      I       Image slot                      Input
      NAME    C*(*)   Gildas Data Frame name            Input
      ERROR   L       Logical error flag              Output
 Subroutines :
-----------------------------------------------------------------------


      SUBROUTINE GDF_RHSEC(IS,TYPE,ARRAY,SIZE,ERROR)
-----------------------------------------------------------------------
 GDF  Read Header Section
      Find information Gildas Data Frame header
 Arguments
      IS      I       Image slot number               Input
      TYPE    C*12    Information wanted              Input
      ARRAY   I (*)   Array to receive information    Output
      LENGTH  I       Size of array                   Input/Output
      ERROR   L       Logical error flag              Output
 Subroutines :
      SIC_AMBIGS, R4TOR4
-----------------------------------------------------------------------

      SUBROUTINE GDF_WHSEC(IS,TYPE,ARRAY,SIZE,ERROR)
-----------------------------------------------------------------------
 GDF  Write Header SECtion
      Write a descriptor in Header of file.
 Arguments :
      IS      I       Image slot                      Input
      TYPE    C*(*)   Type of section                 Input
```

```
      ARRAY   I(*)    Address of section              Input
      LENGTH  I       Length of section (Words)       Input
      ERROR   L       Logical error status            Output
 Subroutines :
      SIC_AMBIGS, R4TOR4
-----------------------------------------------------------------------
```

## 4.7 Named Commons Handling

```
      SUBROUTINE GDF_READX (Islo,Error)
      SUBROUTINE GDF_READY (Islo,Error)
      SUBROUTINE GDF_READZ (Islo,Error)
-----------------------------------------------------------------------
 GDF  Read Header of the X, Y or Z common area from image slot Islo
      ISLO    Integer         Image Slot number
      ERROR   Logical         Error Flag
-----------------------------------------------------------------------

      SUBROUTINE GDF_WRITX (Islo,Error)
      SUBROUTINE GDF_WRITY (Islo,Error)
      SUBROUTINE GDF_WRITZ (Islo,Error)
-----------------------------------------------------------------------
 GDF  Write Header from the X, Y or Z common area to image slot Islo
      ISLO    Integer         Image Slot number
      ERROR   Logical         Error Flag
-----------------------------------------------------------------------

      SUBROUTINE GDF_CHXY, GDF_CHYZ, GDF_CHXZ
-----------------------------------------------------------------------
 GDF  Copy Header of the X, Y or X common into Y, Z, Z respectively
      and move memory pointers accordingly.
-----------------------------------------------------------------------
```

## 4.8 Creating GILDAS Tasks

GILDAS tasks (e.g. for task "`taskname`") are composed of 4 different parts :

- The program, `taskname.exe`.
- The initialization file, `taskname.init`, read by commands `RUN` and `SUBMIT` to get from the user the task input parameters.
- The checker file, `taskname.check`, read by commands `RUN` and `SUBMIT`, to check the input parameters and pass them to the task.
- A help text file, `taskname.hlp`

All files must be located in the `GILDAS_RUN:` directory.
The structure of the program should always be the same :

- An input parameters definition part. No image creation or access should be made before all parameters are defined.
- An input and output image mapping part. If possible all necessary images should be defined in this part.

- One or more subroutines performing the processing. No new image should be created or accessed in the subroutines. The subroutines should preferably not make any reference to any common.
- A cleanup part. An error status should be returned to the system in case of error through a call to SYSEXI.

## 4.9 A Template Task

The following program is a typical task with two input images and an output one. The easiest way to create a new task is just to start with this working template and modify what is needed.

### 4.9.1 Source code

```
        PROGRAM COMBINE
C-------------------------------------------------------------------
C GILDAS Combine in different ways two input images
C        (or data cubes)...
C S.Guilloteau 8-June-1986
C-------------------------------------------------------------------
        INCLUDE 'inc:xpar.inc'
        INCLUDE 'inc:ypar.inc'
        INCLUDE 'inc:zpar.inc'
        INCLUDE 'inc:format.inc'
        INCLUDE 'inc:errcod.inc'
*
        CHARACTER*80 NAMEX,NAMEY,NAMEZ, CODE*20
        LOGICAL ERROR
        REAL AY,AZ,TY,TZ,B,C
        INTEGER I, J, N, M, LENC
        INTEGER IPX, IPY, IPZ, MEMORY(1), POINTER
        INTEGER BLC(4), TRC(4)
        DATA BLC /4*0/, TRC /4*0/
*
        CALL GILDAS_OPEN
        CALL GILDAS_CHAR('Z_NAME$',NAMEZ)
        CALL GILDAS_REAL('Z_FACTOR$',AZ,1)
        CALL GILDAS_REAL('Z_MIN$',TZ,1)
        CALL GILDAS_CHAR('Y_NAME$',NAMEY)
        CALL GILDAS_REAL('Y_FACTOR$',AY,1)
        CALL GILDAS_REAL('Y_MIN$',TY,1)
        CALL GILDAS_CHAR('X_NAME$',NAMEX)
        CALL GILDAS_REAL('BLANKING$',B,1)
        CALL GILDAS_REAL('OFFSET$',C,1)
        CALL GILDAS_CHAR('FUNCTION$',CODE)
        CALL GILDAS_CLOSE
*
        N = LENC(NAMEZ)
        IF (N.EQ.0) GOTO 100
        CALL SIC_PARSEF(NAMEZ(1:N),Z_FILE,' ','.GDF')
        CALL GDF_GEIS (Z_ISLO,ERROR)
        IF (.NOT.ERROR) CALL
     +        GDF_REIS (Z_ISLO,Z_TYPE,Z_FILE,Z_FORM,Z_SIZE,ERROR)
        IF (ERROR) THEN
            WRITE(6,*) 'F-COMBINE,  Cannot read input file'
            GOTO 100
```

```
        ENDIF
        CALL GDF_READZ(Z_ISLO,ERROR)
*
        N = LENC(NAMEY)
        IF (N.EQ.0) GOTO 100
        CALL SIC_PARSEF(NAMEY(1:N),Y_FILE,' ','.GDF')
        CALL GDF_GEIS (Y_ISLO,ERROR)
        IF (.NOT.ERROR) CALL
     +        GDF_REIS (Y_ISLO,Y_TYPE,Y_FILE,Y_FORM,Y_SIZE,ERROR)
        IF (ERROR) THEN
            WRITE(6,*) 'F-COMBINE,  Cannot read input file'
            GOTO 100
        ENDIF
        CALL GDF_READY(Y_ISLO,ERROR)
        IF (Z_EVAL.GE.0.0) Z_EVAL = MAX(Z_EVAL,ABS(Z_BVAL*1E-7))
        IF (Y_EVAL.GE.0.0) Y_EVAL = MAX(Y_EVAL,ABS(Y_BVAL*1E-7))
*
* Check input dimensions
        DO I=1,4
            IF (Y_DIM(I).NE.Z_DIM(I)) THEN
                N = 1
                DO J=I,4
                    N = N*Z_DIM(J)
                ENDDO
                IF (N.NE.1) THEN
                    WRITE(6,*) 'F-COMBINE,  Input images are non coincident'
                    GOTO 100
                ELSE
                    WRITE(6,*) 'W-COMBINE,  Combining a cube with a plane'
                ENDIF
            ENDIF
        ENDDO
*
        N = LENC(NAMEX)
        IF (N.EQ.0) GOTO 100
        CALL SIC_PARSEF(NAMEX(1:N),X_FILE,' ','.GDF')
        CALL GDF_GEIS (X_ISLO,ERROR)
        IF (ERROR) GOTO 100
        CALL GDF_CHYX
        X_BLAN = 2
        X_BVAL = B
        X_EVAL = 0.0
        X_EXTR = 0
        CALL GDF_WRITX(X_ISLO,ERROR)
        CALL GDF_CRIS (X_ISLO,X_TYPE,X_FILE,X_FORM,X_SIZE,ERROR)
        IF (ERROR) THEN
            WRITE(6,*) 'F-COMBINE,  Cannot create output image'
            GOTO 100
        ENDIF
*
        N = Z_SIZE
        M = X_SIZE/Z_SIZE
        CALL GDF_GEMS (X_MSLO,X_ISLO,BLC,TRC,X_ADDR,X_FORM,ERROR)
        IF (ERROR) GOTO 100
```

```
        CALL GDF_GEMS (Y_MSLO,Y_ISLO,BLC,TRC,Y_ADDR,Y_FORM,ERROR)
        IF (ERROR) GOTO 100
        CALL GDF_GEMS (Z_MSLO,Z_ISLO,BLC,TRC,Z_ADDR,Z_FORM,ERROR)
        IF (ERROR) GOTO 100
        ipx = pointer(x_addr,memory)
        ipy = pointer(y_addr,memory)
        ipz = pointer(z_addr,memory)

        IF (CODE.EQ.'ADD') THEN
            CALL ADD002(memory(ipZ),memory(ipY),memory(ipX),
     +                  N,M,
     +                  Z_BVAL,Z_EVAL,AZ,TZ,
     +                  Y_BVAL,Y_EVAL,AY,TY,
     +                  X_BVAL,C)
        ELSEIF (CODE.EQ.'DIVIDE') THEN
            CALL DIV002(memory(ipZ),memory(ipY),memory(ipX),
     +                  N,M,
     +                  Z_BVAL,Z_EVAL,AZ,TZ,
     +                  Y_BVAL,Y_EVAL,AY,TY,
     +                  X_BVAL,C)
        ELSEIF (CODE.EQ.'MULTIPLY') THEN
            CALL MUL002(memory(ipZ),memory(ipY),memory(ipX),
     +                  N,M,
     +                  Z_BVAL,Z_EVAL,AZ,TZ,
     +                  Y_BVAL,Y_EVAL,AY,TY,
     +                  X_BVAL,C)
        ELSEIF (CODE.EQ.'OPTICAL_DEPTH') THEN
            CALL OPT002(memory(ipZ),memory(ipY),memory(ipX),
     +                  N,M,
     +                  Z_BVAL,Z_EVAL,AZ,TZ,
     +                  Y_BVAL,Y_EVAL,AY,TY,
     +                  X_BVAL,C)
        ELSE
            WRITE(6,*) 'Invalid operation code '//CODE
            GOTO 100
        ENDIF
*
* Update disk files and free memory
        CALL GDF_FRIS(X_ISLO,ERROR)
        CALL GDF_FRIS(Y_ISLO,ERROR)
        CALL GDF_FRIS(Z_ISLO,ERROR)
*
        STOP 'S-COMBINE,  Successful completion'
*
98      WRITE(6,*) 'F-COMBINE,  Missing parameter'
100     CALL SYSEXI (FATALE)
        END
*
*
**
        SUBROUTINE ADD002(Z,Y,X,N,M,BZ,EZ,AZ,TZ,BY,EY,AY,TY,BX,C)
C-----------------------------------------------------------------------
C TASK  Internal routine
C       Linear combination of input arrays
```

```
C       X = Ay*Y + Az*Z + C
C Arguments
C       Z               R*4(*)  Input array (N)
C       Y               R*4(*)  Input array (N,M)
C       X               R*4(*)  Output array (N,M)
C       N,M             I       Dimensions of arrays
C       BX,BY,BZ        R*4     Blanking values
C       EY,EZ           R*4     Tolerance on blanking
C       AZ,AY           R*4     Multiplicative factor of array Z, Y
C       TZ,TY           R*4     Threshold on Z,Y
C       C               R*4     Additive constant
C-----------------------------------------------------------------------
        INTEGER N,M
        REAL Z(N),Y(N,M),X(N,M),BX,BY,BZ,EY,EZ,AZ,AY,TY,TZ,C
        INTEGER I,K
*
        DO K=1,M
            DO I=1,N
                IF (ABS(Z(I)-BZ).GT.EZ .AND. ABS(Y(I,K)-BY).GT.EY
     +          .AND. Z(I).GT.TZ .AND. Y(I,K).GT.TY) THEN
                    X(I,K) = AY*Y(I,K) + AZ*Z(I)  +  C
                ELSE
                    X(I,K) = BX
                ENDIF
            ENDDO
        ENDDO
        END
```

### 4.9.2 Initialization file

The initialization file is a standard **SIC** procedure containing only commands from the languages `TASK\` or `SIC\`. `TASK\` language must be specified explicitly. The command syntax is always the following

`TASK\Type_of_parameter "Prompt string" Parameter$[Dimension]`

where

- `Type_of_Parameter` can be `CHARACTER, REAL, INTEGER or LOGICAL`
- `"Prompt string"` is a text used as a prompt if required
- `Parameter$` is the parameter name, the parameter being a standard **SIC** variable, possibly with one dimension. It is recommended to include a `$` as last character to avoid possible confusion with user declared variables.

```
!
! Combine.INIT
TASK\FILE "First input map" Z_NAME$
TASK\REAL "Scaling factor" Z_FACTOR$
TASK\REAL "Threshold" Z_MIN$
TASK\FILE "Second input map" Y_NAME$
TASK\REAL "Scaling factor" Y_FACTOR$
TASK\REAL "Threshold" Y_MIN$
TASK\FILE "Output map" X_NAME$
TASK\REAL "New blanking value" BLANKING$
TASK\REAL "Output offset" OFFSET$
TASK\CHARACTER "Function" FUNCTION$
TASK\GO                     ! Must be last command
```

The parameter names, types and dimensions must correspond to those declared in the source code. All parameters must be defined.

### 4.9.3 Checker File

The checker file is another **SIC** procedure containing only `TASK\` and `SIC\` commands, which tests the validity of the input parameters (to avoid submission of tasks with bad parameters), and writes the parameters. Checking is optional and can be done using **SIC** facilities. All parameters are known **SIC** variables. Writing is done using command `TASK\WRITE`, and the ordering must match the source code. The task is initiated by the `TASK\GO` command.

```
!
! Combine.CHECK
SIC\IF (FUNCTION$.EQ."ADD") THEN
    SIC\SAY "Computing X_NAME = -
    'Y_FACTOR$'*Y_NAME + 'Z_FACTOR$'*Z_NAME + 'OFFSET$'"
SIC\ELSE IF (FUNCTION$.EQ."DIVIDE") THEN
    SIC\SAY "Computing X_NAME = -
    'Y_FACTOR$'*Y_NAME / 'Z_FACTOR$'*Z_NAME + 'OFFSET$'"
SIC\ELSE IF (FUNCTION$.EQ."MULTIPLY") THEN
    SIC\SAY "Computing X_NAME = -
    'Y_FACTOR$'*Y_NAME * 'Z_FACTOR$'*Z_NAME + 'OFFSET$'"
SIC\ELSE
    SIC\SAY "Invalid operation 'FUNCTION$'"
    SIC\RETURN   ! Return without a GO command : no submission
SIC\ENDIF
!
TASK\WRITE Z_NAME$
TASK\WRITE Z_FACTOR$
TASK\WRITE Z_MIN$
TASK\WRITE Y_NAME$
TASK\WRITE Y_FACTOR$
TASK\WRITE Y_MIN$
TASK\WRITE X_NAME$
TASK\WRITE BLANKING$
TASK\WRITE OFFSET$
TASK\WRITE FUNCTION$
TASK\GO                     ! Effectively RUNs or SUBMITs the task.
```

### 4.9.4 The HELP file

A standard help file should be prepared for each task. The format follows that of **SIC** help files. Topics are identified by a "1" in first column, and subtopics by a "2". The help file must start with the task name as main topic, and must have a subtopic for each parameter. More subtopics may exist. The help file must be in the same place as the executable image, and have file type `.hlp`. For the example above, `combine.hlp` contains

```
1 COMBINE
                                COMBINE

     It makes "combinations" of two input images to  produce  a  third
one.   The two input images may have the same dimensions, or the first
one (Z one) may have less dimensions than the second (Y) one.  In  the
latter case, combinations will occur for all the extra planes of the Y
```

```
image.  For example you can divide all the plane of an input  (Y)  3-D
cube  by  a 2-D (Z) image, provided each plane of the cube matches the
single image...

     Operations are
        ADD             X = Ay*Y + Az*Z + C
        MULTIPLY        X = Ay*Y * Az*Z + C
        DIVIDE          X = Ay*Y / Az*Z + C
provided Y > Ty and Z > Tz, where Ty and Tz and thresholds
set by parameters YMIN$ and ZMIN$.

2  Z_NAME$
This is the  name  of  the  input  map  with  the  smaller  number  of
dimensions.
2  Z_FACTOR$
This is a scaling factor for map Z_NAME$.
2  Z_MIN$
This is a threshold on map Z_NAME$.
2  Y_NAME$
This is  the  name  of  the  input  map  with  the  larger  number  of
dimensions.
2  Y_FACTOR$
This is a scaling factor for map Y_NAME$.
2  Y_MIN$
This is a threshold on map Y_NAME$.
2  X_NAME$
This is the name of the output map.
2  BLANKING$
This is the blanking value chosen for the output map.
2  OFFSET$
This is an offset added to the output map.
2  FUNCTION$
Selected operation.  Possible operations are ADD, MULTIPLY, DIVIDE  (Y
by Z).
```

## 4.10 Debugging Tasks

In addition to the predefined directory, `GILDAS_RUN:`, another directory `GILDAS_LOCAL:` is also searched for tasks by commands `VECTOR\RUN` and `VECTOR\SUBMIT`. This area is searched before `GILDAS_RUN:`. If the required task is found here, the initialisation, checker and help files should also be present in the same directory. This feature allows to have experimental or user-private tasks.

Although the tasks are supposed to be non-interactive programs spawned or submitted from a main program, interactive use is possible for debugging purpose. If activated interactively, a task will ask one question for each parameter, specifying the parameter type, the parameter name, and the parameter dimension. No more information will be available. The initialization and checker file are not needed for this.

Moreover since all algorithms can be standard subroutines due to the use of virtual memory, the **GILDAS** interface can be done easily after debugging the algorithm.

# 5 GTVIRT Programming Manual

## 5.1 Concept

The GTVIRT is a fast low-level Graphic library, allowing to develop Graphic programs in a completely device independent way. The GTVIRT library involves the following concepts:

- *the Plot Page*
  The Plot Page is a virtual workspace on which all graphic items will be (virtually) drawn. The Plot Page units are "virtual centimeters". Actual drawing on a graphic device is usually done with an automatic scaling factor to match the Plot Page to the device. For hardcopy outputs, an exact matching between the Plot Page unit and centimeters is possible.

- *Segments*
  Graphic segments are the smallest separable entities in a drawing. Segments are named, and can be edited to change their aspects. Although segments are usually associated with a single, easily identified, part of the drawing (e.g. a curve, or a label, or a bitmap image), they can contain anything. The segmentation is not defined by the GTVIRT, but left to the calling program. Segments are named uniquely to help identifying them.

- *Coordinate Systems* Two coordinate systems are available within the GTVIRT: a Page coordinate system (whose units are centimeters), and a User coordinate system. Drawing can be done in any of these systems.

- *Directories*
  Directories are special graphic segments used to group in a logical way ensembles of segments. A complete directory tree can be specified in a drawing. As for the segments, the structure of the drawing is defined by the calling program, not by the GTVIRT library.

  Each directory has its own User coordinate system. This feature can be used to map several coordinate systems to different or similar regions of the Plot Page.

- *Devices*
  The GTVIRT is (completely ?) device independent. A drawing can be prepared and visualized separately. The GTVIRT allows display on a large variety of graphic devices.

- *Metafiles*
  Directories and directory trees of a Plot can be saved on a (binary) metafile, complete with all graphic segments and user coordinate systems. Metafiles can be imported as Sub-directories in any Plot.

- *Hardcopy*
  "Hard"copy on paper-like Graphic devices such as pen plotters, laser printers, etc..., are completely transparent in the GTVIRT. "Soft" hardcopy on files in industry standard graphic languages such as PostScript or HPGL is possible too.

- *Windows*
  *Windows* are available on some devices. This includes X-Window terminals, and MS-Windows screen. *Windows* can be attached to any directory. Several windows can be attached to the same directory. A *Window* displays all the sub-directories depending on the directory to which it is attached.

- *Plotting Depth*
  Each segment can be understood as an opaque or transparent plot. The order in which opaque segments are plotted can be controlled by their plotting depth. This feature is important when plotting bitmaps or drawing colour filled curves.

- *8-bit images*
  are supported on Windows graphic displays (X-Window or MS-Window or MAC).

The **GTVIRT** normally operates in a buffered mode. All drawings command a written into an internal metacode, and only transmitted to the plotting device when required by the calling program. In addition, for applications which require an unbuffered plot, an *immediate* mode is available.

## 5.2 Programming

- Initialisation
  The GTVIRT library is initialized by a a call to
  `SUBROUTINE INIT_GTVIRT`
  followed by a call to `SUBROUTINE GTINIT(LX,LY,LUNG,LUNH,NAME,USER_ROUTINE`
  where
  - `LX,LY` are the page dimensions
  - `LUNG,LUNH` are logical unit numbers for graphic output and hardcopies, to be supplied by the caller
  - `NAME` is a character string giving the name of the top directory of the drawings. `NAME` should start with a < sign.
  - `USER_ROUTINE` is a user-supplied subroutine called when moving from a sub-directory to the other. It must provide to the GTVIRT information about coordinate systems. The only suitable routine is available in the **GreG** program, and is named `GREG_USER`
- The `GTVIEW` subroutine

  The `GTVIEW` subroutine is one of the main control routine in the library. It is used to send drawing commands from the internal metacode to the graphic device, but also to performs other actions on the metacode.

  `SUBROUTINE GTVIRT(Mode)`

  where `Action` is a character string which can be
  - 'Append'
    Plot all metacode starting from last drawn vector
  - 'Rewind'
    Clear the screen, and plot the whole metacode from first vector
  - 'Update'
    Update the screen (all windows) if needed
  - 'Limits'
    Recompute the plot limits (Bounding Box)
  - 'Purge'
    Delete images associated to all windows
  - 'Delete'
    Delete images associated to the current window
  - 'Zap'
    Delete cache-bitmap associated to images
  - 'Sleep'
    Set screen update off
  - 'Wake'
    Set screen update on

## 5.3 Basic Sequence

**GreG** and the **GTVIRT** are intimately related, and it is not recommended to use the **GTVIRT** without **GreG**Åccordingly, the programming example given below also uses some (primitive) **GreG** subroutines. The basic drawing sequence is

```
CALL GR_SEGM (Segment_Name,Error)   ! 1
CALL GTPOLYL (N,Xarray,Yarray)      ! 2
CALL ...                            ! 3
CALL GTVIEW('Append')               ! 4
```

1. Open a new graphic segment. This routines is an "intelligent" routine checking wether pen attributes have been changed, and calling both `GTSEGM` (the basic segment creation routine) and `GTEDIT` (which defines the segment attributes like pen colour, dashed pattern, thickness).
2. Use any drawing routine you wish, e.g. an polyline. The drawing commands go to the internal metacode only at that time.
3. ...
4. Update the graphic screen with all the new drawing commands which have been put in the metacode since last call to `GTVIEW('Append')`

Further buffering between graphic segments can be obtained by enclosing a set of complete sequences like the above one between a call to `GTVIEW('Sleep')` and `GTVIEW('Wake_up')`. Drawing to the screen will then only happen when the call to `GTVIEW('Wake_up')` is made. For compatibility with other subroutines which may also perform their own `Sleep / Wake_up` control, it is recommended to use the logical function `GTSTAT` instead, e.g.

```
      SLEEP = GTSTAT ('Sleep')

... calls to GTVIRT ...

      IF (.NOT.SLEEP) CALL GTVIEW('Wake_up')
```

## 5.4 Plot Structuration and multi-window applications

For some complex applications, it is useful to be able to create several graphic windows and display different plots in each of them. Such a control over the plot structure is preferably done using the `GTVL` command language, by appropriate calls to subroutine `GR_EXECL`.

`SUBROUTINE GR_EXECL(Command)`
execute a command from the `GTVL` command language.

The most relevant commands to structure a plot are

- `CREATE DIRECTORY <NAME` to create new top directory called `<NAME`
- `CHANGE DIRECTORY <NAME` to move to this (top) directory
- `CREATE WINDOW` to create a new window associated to the current directory
- `CHANGE POSITION Code` to move the current window a given position in the screen.
- `CLEAR WINDOW` to clear a window
- `CLEAR TREE` to erase the tree linked to the current directory (from the current top directory).
- `CREATE DIRECTORY NAME` to create new sub directory
- `CHANGE DIRECTORY NAME` to move to this sub directory

Refer to the **GreG** manuals for detailed help on these commands.

In addition, subroutine `GTEXIST` is useful to check whether a given directory already exists.

## 5.5 Subroutines

- gtalph
  Commute to alphanumeric mode. On Windows system, transfer focus to the terminal window.
- gtchar
  Draws a character string.
- gtclal
  Clear alphanumeric screen. On Windows applications, transfer focus to the (current) graphic window, and raise in on top of others to display it.
- gtclear
  Erase the whole plot, all directory structures, destroy all associated windows, etc... An empty top directory is then re-created
- gtclos
  Close the current graphic device
- gtclpl
  Raise alphanumeric window, and returns focus to it.
- gtcurs
  Call the cursor
- gtdls
  Delete the last graphic segment
- gtdraw
  Draw a vector from current pen position to the specified point.
- gtedit
  Edit the current segment properties.
- gterflag, gterrgto, gterrtst
  Control error status of the library
- gtexist
  Controls the existence of a named sub-directory.
- gthard
  Create a hardcopy
- gtinit
  Initialize the GTVIRT drawing space and the GTVL language
- gtopen
  Open a graphic device
- gtpolyl
  Draw a set of lines.
- gtreloc
  Move current pen position to specified coordinates.
- gtsegm
  Open a new segment
- gtview
  Activate the drawing

- gtwhere
  Returns current pen position
- gtg_charlen
  Computes character string length
- gtg_charsiz
  Returns character size
- gtg_curs
  Returns cursor existence
- gtg_screen
  Returns clipping parameters
- gtg_open
  Returns device parameters
- gtstat
  Change GTVIRT mode (Sleep or Wake_up), and returns previous mode.
- gtv_newimage
  Create a new image slot
- gtv_image
  Draw a bitmap to an image slot
- gtv_numimage
  Get a free image slot
- gtv_majimage
  Define parameters of an image slot
- gtv_fillpoly
  Fill a closed polygon.
- init_gtvirt
  Initialize the GTVIRT library
- exit_clear
  Quick exit, to be used at program completion.
- run_gtvl
  Dispatch the GTVL commands to appropriate subroutines
- exec_gtvl
  Execute a GTVL language command or command procedure

*Immediate* routines are used to produce immediate actions. They use the immediate pen. These subroutines are

- gti_beep: beep
- gti_clear: clear the current window
- gti_draw: draw line to current
- gti_out: flush the normal drawing buffer.
- gti_pen: select the immediate pen
- gti_polyl: draw a polyline
- gti_reloc: relocate the immediate pen
- gti_where: returns immediate pen position

# Index


EXAMPLE
- ENTER_USER, 7
- EXEC_USER, 7
- PLAY_USER, 7
- RUN_USER, 8
- US_ERROR, 11
- US_EXEC, 11

ROUTINES
- FREE_VM, 22
- GAGOUT, 13
- LENC, 22
- SIC_AMBIGS, 20
- SIC_ANALYSE, 12, 21
- SIC_CH, 10, 19
- SIC_CTRLC, 19
- SIC_DEF_CHAR, 14
- SIC_DEF_DBLE, 14
- SIC_DEF_FUNC, 16
- SIC_DEF_INTE, 14
- SIC_DEF_LOGI, 14
- SIC_DEF_REAL, 14
- SIC_DELSYMBOL, 22
- SIC_DELVARIABLE, 16
- SIC_DESCRIPTOR, 15
- SIC_FORMAT, 12, 21
- SIC_GET_CHAR, 14
- SIC_GET_DBLE, 14
- SIC_GET_INTE, 14
- SIC_GET_LOGI, 14
- SIC_GET_REAL, 14
- SIC_GETLUN, 13
- SIC_GETSYMBOL, 22
- SIC_GETVM, 21
- SIC_I4, 10, 19
- SIC_INCARNATE, 16
- SIC_INSERT, 18
- SIC_INTER_STATE, 19
- SIC_KE, 10, 19
- SIC_L4, 10, 19
- SIC_LANG, 12, 19
- SIC_LEN, 21
- SIC_LET_CHAR, 14
- SIC_LET_DBLE, 14
- SIC_LET_INTE, 14
- SIC_LET_LOGI, 14
- SIC_LET_REAL, 14
- SIC_LIRE, 18, 19
- SIC_LOAD, 4, 12, 18
- SIC_LOG, 19
- SIC_LOGICAL, 16
- SIC_LOWER, 22
- SIC_MATH, 16
- SIC_NARG, 20
- SIC_NEXT, 21
- SIC_OPT, 5, 18
- SIC_PARSEF, 22
- SIC_PRESENT, 20
- SIC_R4, 10, 19
- SIC_R8, 10, 19
- SIC_RUN, 7, 17
- SIC_SETSYMBOL, 22
- SIC_SEXA, 16
- SIC_START, 21
- SIC_UPPER, 22
- SIC_VOLATILE, 16
- SIC_WPR, 22
- SIC_WPRN, 22
- VAR_TYPE, 15

SIC
- MEMORY, 5