A manual of Difmap help pages

Martin Shepherd (mcs@astro.caltech.edu)
Copyright ©1993 California Institute of Technology

April 24, 1998

The list of commands in difmap.

addcmp 32
Add a model component by hand to the tentative model.
addhist 34
Append a new line to the recorded history of an observation.
addwin 35
Append a new entry to the list of clean windows.
basename 36
Returns the name of baseline 'ibase' of sub-array 'isub'.
beamloc 37
Change when and where mapplot plots the clean beam ellipse.
clean 39
Clean a residual dirty map with the dirty beam.
clrhist 42
Clear the history information recorded with the observation.
clrmod 43
Clear one or more of the established, tentative and continuum models.
clroff 45
Undo all resoff calibration-offsets applied during this difmap session.
corplot 46
Display accumulated telescope based self-cal corrections versus UT.
cpplot 48
Interactive display and editing of observed and model closure phases.
delwin 56
Delete all clean windows.
edmodel 57
Modify the established and tentative models with an external editor.
get 60
Restore UV data, models and windows from files.
gscale 62
Self calibrate to determine overall telescope amplitude corrections.
header 65
List useful parts of the observation header on one's terminal.
imstat 66
Return image plane map statistics.
invert 68
Grid selected UV data and Fourier invert it to a (residual) dirty map
keep 71
Establish the latest CLEAN model and compute its UV representation.
loglevs 72
Set logarithmic contour levels for mapplot.
mapcolor 74
Select the colormap type, brightness and contrast to use in mapplot.
mapfunc 77
Change the transfer function and data range displayed in mapplot.
maplot 79
Alternative name for the mapplot command - see help mapplot.
mapplot 80
Display the dirty beam, residual or restored map and modify CLEAN windows.

mapsize 87
Request a new map grid of given width and cell size
mapunits 90
Change the units used to specify and label map and UV plane distances.
mapvalue 92
Return the value of the map pixel nearest to a given coordinate.
modelfit 93
Fit image-plane model components to visibilities in the UV plane.
nbase 96
Return the number of baselines in a given sub-array.
nchan 97
Return the count of the number of spectral-line channels per IF.
nif 98
Return the number of IFs in the current observation.
nsub 99
Return the number of sub-arrays in the current observation.
ntel 100
Return the number of telescopes in a given sub-array.
observe 101
Read UV data from a random-groups UV FITS file.
peak 104
Return details of the min,max or absolute max flux in a map.
peakwin 106
Place a CLEAN window around the brightest pixel in the residual map.
projplot 107
Plot visibility amplitudes and/or phases versus projected UV distance.
radplot 112
Plot visibility amplitudes and/or phases versus UV radius.
resoff 117
Determine and apply a baseline based amplitude and phase correction.
restore 119
Add the CLEAN model to the residual map to form a clean map.
rmodel 122
Read a new CLEAN model from a VLBI model file.
rwins 124
Read windows previously saved CLEAN windows from a text file.
save 125
Save UV data, models, windows, the restored map and a command file.
scangap 128
Change the time gap used to delimit neighboring scans.
select 130
Select a polarization and ranges of spectral-line channels to be processed.
selfant 134
Set antenna based constraints for subsequent self-calibration.
selfcal 137
Self calibrate for telescope phase (and amplitude) corrections.
selfflag 141
Control the identification and fate of un-correctable visibilities.
selflims 144
Set limits on acceptable amplitude and phase corrections in selfcal.

selftaper 146
Sets a (1 - gaussian) taper to weight down SHORT baselines.
setcont 148
Add the current model to the continuum model.
shift 151
Shift the observation phase-center, CLEAN window and model positions.
showhist 153
Display the history that was recorded with the current observation.
showpar 154
Display a list of difmap configuration parameters.
specbase 155
Select baselines to be displayed by specplot.
specopt 158
Preset specplot display options.
specorder 160
Set the order in which specplot plots spectra.
specplot 163
Plot time-averaged visibility spectra.
specpol 169
Select the list of polarizations to be displayed by specplot.
specsmooth 171
Preset the spectral resolution displayed by specplot.
spectime 174
Select the range(s) of times to be averaged by the specplot command.
specuvr 176
Select the UV radius ranges to be displayed by specplot.
startmod 178
Read a starting model from disk and phase self-calibrate against it.
telname 180
Returns the name of telescope 'itel' of sub-array 'isub'.
tplot 182
Plot time sampling for each telescope of an observation.
uncalib 186
Undo recorded telescope calibrations (eg. self-cal corrections).
unshift 188
Undo accumulated position shifts from the data, windows and models.
uvaver 189
Time average a UV data set.
uvplot 191
Plot observed UV points on the UV plane.
uvrange 195
Set the min and max UV radii of usable visibilities for gridding.
uvstat 197
Return UV plane visibility statistics.
uvtaper 198
Set a gaussian taper to weight down long baselines and reduce sidelobes
uvweight 200
Set the type and degree of weighting for subsequent UV gridding.
uvzero 202
Set the estimated flux expected from a baseline of zero length.

vplot 204
General visibility plotting and editing command.
wbeam 212
Save the dirty beam to a FITS file.
wdmap 213
Save the residual dirty map to a FITS file.
winmod 214
Delete all components outside (or inside) the current clean windows.
wmap 215
Save the clean (restored) map to a FITS file.
wmodel 216
Write CLEAN models to a VLBI model file.
wobs 217
Save UV data to a random-groups UV FITS file.
wtscale 218
Change the scale factor that mutiplies the raw visibility weights.
wwins 220
Save CLEAN windows to a text file.
xyrange 221
Set the bounds of the sub-image to be displayed in mapplot.

The list of difmap help topics.

antenna_names 6
A description of the format of telescope specifications.
editing 10
General discussion of editing in difmap.
models 13
An overview of how models are used in difmap.
multi_if 18
An overview of multi-IF mapping.
polarization 21
Overview of Difmap polarization mapping.
spectral_line 23
An overview of the current spectral-line facilities.
subarrays 27
A discussion of sub-array handling in Difmap.
whatsnew ..... N/A
The details of recent difmap changes.

Difmap help topics

The following pages show the contents of each of the Difmap help topics. The same pages can be seen from whithin Difmap by typing:

help name_of_topic

antenna_names

A description of the format of telescope specifications.

Many Difmap commands expect you to select one or more sub-arrays, antennas, baselines, or closure triangles. To make this easier, a consistent syntax is used to specify all such telescope aggregates. This specification of an aggregate of n>=0 telescopes is of the form:

```
 [sub-array:][antenna_1 antenna_n...]
```

Where "sub-array" is a number between 1 and nsub, and antenna_n is an exactly matching or an otherwise unambiguous prefix of an antenna name.

[Sub-array]

The sub-array index is optional and defaults to a context dependent value. From the command line it generally defaults to sub-array 1. Within interactive commands, such as vplot, it defaults to whatever sub-array is currently being viewed.

If both a sub-array index and one or more antenna names are specified, the first antenna name must be separated from the sub-array index with a colon (:). Otherwise the colon is optional. A colon without a preceding sub-array index implies selection of the default sub-array.

[antenna_1 ...antenna_n]

If a telescope aggregate is made up of n telescopes then there may be up to n antenna names specified. Omitted trailing antenna names are treated as wild-cards.

Omitting trailing components of a specification

For non-interactive commands, omitting one or more trailing components from a specification is interpreted to mean that all telescope aggregates of the expected type (eg. a sub-array or baseline aggregate...) that match in the initial specified components, are acceptable. The omission is thus effectively a wild-card. For interactive commands, such as vplot, which won't plot all the wild-carded aggregates without further user direction, the first aggregate that matches in the initial given indexes is sought and the selection is then forgotten. Thus to the vplot command an empty specification string "" means plot all baselines of all sub-arrays when plotting to a non-interactive device, whereas on an interactive device the same specification would mean start plotting from the first baseline in the default sub-array.

EXAMPLES

The following examples illustrate how specifications are interpreted in different contexts. Note that while each specification is shown enclosed within quotes, this is to make it possible to display an empty string. In practice quotes are only legal for specifications that are given as command-line arguments to commands, and even there they are rarely necessary. Also note that all difmap commands interpret the omission of a trailing telescope specification argument as equivalent to specifying an empty string.

Sub-array specifications

""	All sub-arrays.
":"	The default sub-array.
"2"	Sub-array 2.

Telescope specifications

""	All telescopes of all sub-arrays.
":"	All telescopes of the default sub-array.
"2"	All telescopes of sub-array 2.
"an1"	Telescope AN1 of the default sub-array.
"2:an1"	Telescope AN1 of sub-array 2.

Baseline specifications

""	All baselines of all sub-arrays.
":"	All baselines of the default sub-array.
"2"	All baselines of sub-array 2.
"an1"	All baselines of telescope AN1 in the default sub-array.
"2:an1"	All baselines of telescope AN1 in sub-array 2.
"an1 an2"	Baseline an1-an2 in the default sub-array.
"2:an1 an2"	Baseline an1-an2 in subarrary 2.

Closure triangle specifications

""	All triangles of all sub-arrays.
":"	All triangles of the default sub-array.
"2"	All triangles of sub-array 2.
"an1"	All triangles of telescope AN1 in the default sub-array.
"2:an1"	All triangles of telescope AN1 in sub-array 2.
"an1 an2"	All triangles of baseline an1-an2 in the default sub-array.
"2:an1 an2"	All triangles of baseline an1-an2 in subarrary 2.
"an1 an2 an3"	Triangle an1-an2-an3 in the default sub-array.

```
  "2:an1 an2 an3"    Triangle an1-an2-an3 in sub-array 2.

SPECIFIC EXAMPLES
-----------------

1. Inspection of the currently selected self-cal constraints
   for one or more telescopes.

   0>selfant ""
   1:AN1      self-cal  status=correctable  weight=1
   1:AN2      self-cal  status=correctable  weight=1
   1:AN3      self-cal  status=correctable  weight=1
   2:AN1      self-cal  status=correctable  weight=1
   2:AN2      self-cal  status=correctable  weight=1
   2:AN3      self-cal  status=correctable  weight=1

   0>selfant 2
   2:AN1      self-cal  status=correctable  weight=1
   2:AN2      self-cal  status=correctable  weight=1
   2:AN3      self-cal  status=correctable  weight=1

   0>selfant an3
   1:AN3      self-cal  status=correctable  weight=1

2. Non-interactive visibility plotting to a hard-copy device.

   0>dev /ps

   0>vplot 0, ""
   Using default options string "efbm3"
   Page 01: baselines of 1:AN1
   Page 02: baselines of 1:AN2
   Page 03: baselines of 1:AN3
   Page 04: baselines of 2:AN1
   Page 05: baselines of 2:AN2
   Page 06: baselines of 2:AN3

   0>vplot 0, 1
   Using default options string "efbm3"
   Page 01: baselines of 1:AN1
   Page 02: baselines of 1:AN2
   Page 03: baselines of 1:AN3

   0>vpl 0, 2:an2
   Using default options string "efbm3"
   Page 01: baselines of 2:AN2

   0>vpl 1, 2:an2 an3
   Using default options string "efbm3"
   Page 01: baselines of 2:AN2
```

editing

General discussion of editing in difmap.

EDITING VISIBILITY DATA

It is rare to find an interferometer data set that is not contaminated with interference, correlator errors or other unwanted observational artifacts. So it is important to be able to flag selected parts of the data to be ignored by future processing, and to be able to undo such flags if it becomes apparent that prior editing was unwarranted.

In Difmap there are currently three types of flagging.

Deleted data.

Visibilities that have been given zero weight, and visibilities which do not appear in the input UV FITS file are regarded as "deleted". These visibilities are not displayed in any plots. None of the commands in Difmap change good or flagged data to deleted data, and such data can only come from input UV FITS files. Similarly, there is no way to undelete such data.

Visibility flags.

Individual visibilities can be interactively flagged or unflagged in a number of difmap plot commands, such as vplot, tplot, radplot, projplot and uvplot. When flagged visibilities are displayed, they are plotted in red. When unflagged (good) visibilities are plotted, they are plotted in green.

Correction flags.

Telescope based self-calibration corrections consist of three parts. A phase correction, an amplitude correction and a correction flag. Initially the phase correction is set to zero, the amplitude correction to unity and the flag is not set. To fill in ampitude and phase corrections the 'selfcal' command must be used. This determines new incremental telescope corrections based on the input visibilities and a model. Where there is insufficient information to determine a correction, the correction-flag member is set.

When self-calibration corrections are applied, if a correction is flagged, the flag is also applied to all affected visibilities. These correction flags are recorded in addition to other visibility flags and can be removed without affecting normal visibility flags by running the 'uncalib' command, or by interactively toggling them in the 'corplot' command. In plot commands, visibilities that are flagged due to self-calibration are displayed in blue, to differentiate them

from good visibilities plotted in green and otherwise flagged
visibilities that are plotted in red. Other commands don't
differentiate between the flag types, and thus any visibilities that
are flagged for any reason are ignored.

TELESCOPE VERSUS BASELINE EDITING.

Telescope based editing.

Many observational artifacts are telescope based. For instance loss of
cooling and other receiver problems are always telescope based, whereas
external interference will appear as telescope based problems for
VLBI and VLBA work, but as array-wide problems for compact arrays
such as the VLA.

The 'vplot' command groups baseline plots by telescope. This gives one
the opportunity to determine whether a problem is telescope based, and
to home in on the bad telescope. Telescope highlighting in the
'radplot' command can also be used to search out bad telescope based
artifacts. When such problems are identified, one should display
all baselines of the bad telescope in 'vplot' and select the default
telescope-based editing mode before editing.

Baseline editing.

Fortunately, very few observational artifacts appear as baseline based
errors. This is fortunate because self-calibration is unable to remove
such problems, and correcting them with resoff is a bad idea. Known
ways in which baseline errors can be introduced, are correlator
problems (particularly analogue correlators), telescope-shadowing
and poorly matched receiver bandpasses.

If you intend to use self-calibration then it is always best to use
telescope based editing where pertinent. This is because
self-calibration can get confused by incomplete sampling of a given
telescope. The 'selfcal' command attempts to detect such cases and
flag them rather than make a correction, but there are some cases that
it is not able to detect. One such case is where a telescope is
sampled by two effectively disconnected arrays, because visibilities
that would have connected the two arrays have been flagged. In such
cases there are two possible telescope correction solutions.

Multi-IF editing scope

In plot commands that individually show data of all IFs on a single
plot, edits are applied only to the source IFs of the selected points.
These include the following commands:

  radplot - Plot visibility amplitudes and/or phases versus UV radius.

```
  uvplot  - Plot observed UV points on the UV plane.

In plot commands that by their nature can only plot data from one IF
at time, edits are by default extended over all IFs (except when
restricted by channel-range selections as described below). To
optionally constrain edits to only be applied to the displayed IF, all
of these commands provide a toggleable option, bound to the 'I' key.
The relevant commands are:

 cpplot   - Interactive display and editing of observed and model
            closure phases.
 projplot - Plot visibility amplitudes and/or phases versus projected
            UV distance.
 radplot  - Plot visibility amplitudes and/or phases versus UV radius.
 tplot    - Plot time sampling for each telescope of an observation.
 vplot    - Plot visibility amplitudes and phases versus time.

Polarization editing.
---------------------
In Difmap all edits applied to one polarization are always applied to
all other recorded polarizations. However, be warned that unflagging a
visibility which has one or more polarizations deleted, can not unflag
deleted visibilities, and will thus result in different UV plane
sampling in different polarizations. For the most part this is
irrelevant, since the select command will not attempt to derive
polarizations from combined stokes parameters if one of the
stokes parameter visibilities is flagged or deleted, but if you are
making maps of the individual stokes parameters to later be turned
into percentage polarization maps, the results might be adversely
effected.

Multi-channel editing scope
---------------------------
By default visibility edits are applied to all spectral line channels,
but all plot commands that allow editing, allow one to constrain edits
to the ranges of channels selected with the 'select' command. This
option is toggled with the 'W' key.

Self-calibration correction flag scope.
---------------------------------------
A single self-calibration flag is always effectively applied to all
spectral-line channels and polarizations of a single IF, so the
'corplot' command does not have either the 'I' or 'W' options provided
for normal visibility editting.
```

models

An overview of how models are used in difmap.

DIFMAP MODELS

The term 'model' refers to a mixed list of delta, gaussian and other simple components, which when superposed in the image plane, form a facsimile of the source being mapped. In Difmap this model is split into three parts, an established model, a tentative model and a continuum model.

1. The established model.

   The established model is an incrementally built up model of the source. Not only is it represented by a component list, but its representation in the UV plane is also calculated at the UV coordinate of each observed visibility in the selected processing stream, to form model visibilities.

2. The tentative model.

   The tentative model is a separate component list that represents the latest attempt at modelling the difference between the observed visibilities and the established model visibilities. Since it is expensive to calculate model visibilities, the tentative model is maintained only as a component list. This list is separate from the established model, and it can be discarded at any time via the 'clrmod' command without affecting the established model. Alternatively, when the tentative model is deemed acceptable, it can be installed as part of the established model, via the 'keep' command, which transfers the tentative model to the end of the established model. Note that the 'keep' command is automatically called whenever a command is invoked that requires model visibilities, but it can also be called explicitly by the user to force an earlier transfer.

   The tentative model has its origin in a number of commands:

   The 'clean' command incrementally builds up the tentative model, by clean deconvolution of the latest residual map (formed by inverting the difference between the observed and established model visibilities).

   The 'modelfit' command also uses the tentative model, placing all the variable model components there (after establishing any non-variable components of any existing tentative model.).

   When the 'rmodel' command reads a model from an external file, it

places it directly in the tentative model.

When the 'select' or 'uvaver' commands are called, the UV representation of the established model is no longer valid, so the established model is temporarily demoted by pre-pending it to the tentative model, so that it will be re-established when the 'keep' command is next invoked.

3. The continuum model.

Spectral-line observations are often corrupted by unwanted continuum radiation. The function of the continuum model is to model this continuum emission such that it can dynamically be subtracted from the observed visibilities and then not included in clean maps of spectral-line channels. It is created via the 'setcont' command. In practice, it can be viewed as being part of the established model, in that the model visibilities used to form (observed-model) visibility residuals are actually formed from the superposition of the established and continuum models. The main difference is that the 'restore' command ignores the continuum model when it forms clean maps. A second difference is that since the continuum model is recorded as a separate model component list, the established and/or tentative models for a given spectral-line channel can be discarded without touching the continuum model.

EXAMPLES OF HOW MODELS INTERACT WITH DIFMAP COMMANDS.

The following example shows a typical sequence of commands and how they affect the three difmap models.

First we read in a new observation with the 'observe' command. This clears any existing established, tentative and continuum models.

```
observe file.uvf
```

After setting the map-size and other weighting options, we display the dirty map by typing:

```
mapplot
```

This invokes the 'invert' command to Fourier-invert the observed data and create a dirty map of the source, which is then displayed, allowing us to set up clean windows etc.. At this point there is no model, so all model visibilities have amplitudes and phases of 0, and the map of the residual between the observed and model visibilities is identical to a direct map of the observed data.

Next we decide to clean the map and so type:

```
  clean
```

This partially cleans the area inside any windows that we set in mapplot, or cleans the whole dirty map if no windows were set. The delta-function model components that this generates are appended to the currently empty tentative-model component list.

Again we display the modified residual map by typing:

```
  mapplot
```

but this time we are presented with a map formed from the difference between the new tentative model and the observed data. In this case, since 'clean' itself subtracted these components from the dirty map, there is no need to re-invert the data, so the residual map is displayed directly.

Next, having looked at the residual map, we decide that there are some clear problems with the data, and decide to look at the observed visibilities by typing:

```
  vplot
```

But the 'vplot' command also allows one to display model visibilities alongside the observed visibilities. Thus the 'vplot' command needs the UV representation of the current tentative model. To get this, it automatically calls the 'keep' command, which removes the components of the tentative model, and appends them to the currently empty established model list - at the same time it also calculates their UV representation as model visibilities.

Having finished with the 'vplot' command, probably having editted bad sections of the data, we decide to again look at the residual map by typing:

```
  mapplot
```

but since the model visibilities have been changed by adding in the tentative model, the old residual map is no longer in step with the data, so first the mapplot command calls the 'invert' command to form a new residual map by inverting the residual between the observed and the new established model visibilities. It then displays the new residual map, so that we can set windows etc..

Next we decide to clean the map further by typing:

```
  clean 1000
```

This again adds to the newly emptied tentative model, by performing up to 1000 iterations of clean. Each iteration creates a new

delta-function model component, which is entered into the tentative model. This may not however lead to there being 1000 components listed in the tentative model, because any delta-components that share the same position are combined into a single component.

To see the effect of the latest clean we type:

```
mapplot
```

Since the clean command didn't change either the established model visibilities or the observed visibilities, mapplot directly displays the residual map as the 'clean' command left it. The 'invert' command is not invoked.

At this point from looking at the map we decide that 1000 iterations of clean was far too many, and decide to discard the tentative model that clean generated, by typing:

```
clrmod
```

This doesn't touch the established model, but again, the residual map that clean produced is no longer in step with the data, so the next command that requires the residual map will automatically re-invert the data, as before. Thus when we decide to repeat the clean with fewer iterations, the 'clean' command re-inverts the data for us first.

```
clean 100
```

At this point we look at the residual map again with the mapplot command and notice that our choice of clean windows has allowed 'clean' to place components where they don't make sense. So in mapplot we tighten the windows to only include the areas where we want components and then type:

```
winmod
```

This command deletes all model components that lie outside the current set of clean windows. Again this invalidates the current residual map, which will automatically be re-inverted when the next command that requires the residual map is required. In the process, the current tentative model will be appended to the end of the current established model and its representation in the UV plane added to the exiting established model visibilities.

There are many other commands that involve the three models, but the above example demonstrates the main idea, that in general the user does not have to worry about what is in which model, since each Difmap command knows what it needs and how to get it, without being told.

Other important commands that directly effect the models include:

The 'rmodel' command, used to read in previously generated models from external disk files. This deletes all existing models before reading in the new one.

The 'wmodel' command, used to save models in external disk files.

The 'modelfit' command, used to fit the free parameters of a model to the observed visibilities.

The 'edmodel' command, used to display the current model in your choice of external editor, so that you can edit it directly by hand. This is mainly used when model-fitting to change the set of free parameters.

The 'maplot' command, used as above, but it can also be used to display model components, delete individual model components, and create new model components using the cursor.

The 'setcont' command, used to specify that the current combined model should be moved into the continuum model.

multi_if

An overview of multi-IF mapping.

Mapping multiple IFs in Difmap.

CONTEXT

The word "IF" is as an acronym for "Intermediate Frequency", which refers to the frequency of the receiver stage at which most signal amplification and filtering occurs. In Radio Astronomy the term has been generalized to mean any single signal path between a telescope and the correlator. Thus, a telescope that simultaneously receives two bandpasses centered at different frequencies, is said to have two IFs. This should be distinguished from the multiple frequency channels of spectral-line observations, where a single bandpass is split into multiple channels during, or after correlation.

UV FITS RESTRICTIONS

Random groups UV FITS files impose certain constraints on IFs. In particular, although each IF is usually centered at a different frequency, the number of spectral-line frequency channels, and the number and types of stokes parameters in each IF, must be identical.

DIFMAP RESTRICTIONS

In addition to the general restrictions imposed by random-groups UV FITS files, there are other restrictions imposed by Difmap.

While Difmap does accept most multi-IF UV FITS files, it rejects those in which the frequencies assigned to the IFs change during the observation. In AIPS parlance, this can be restated by saying that Difmap rejects any file that has multiple frequency IDs in its FQ table.

Mapping multiple IFs in Difmap.

Before mapping a multi-IF observation, one should decide which IFs to map first. For continuum this will normally be all IFs, whereas for spectral-line it is more likely to be a group of spectral-line channels from a single IF. The 'select' command caters for both of these choices, along with others. It takes a polarization name, and one or more spectral-line channel ranges for each IF. IFs of continuum observations are regarded as single-channel spectral-line IFs. For each IF in which channels are selected, the 'select' command forms a psuedo-continuum channel by averaging together visibilities of those channels. One is left with one or more psuedo-continuum IFs, known as the current processing stream. Most commands operate on this

stream. The major exception to this rule is that edits and other corrections are applied to the original data as well as to the current stream. In addition the following commands work directly on the complete data-set and ignore the current stream selection:

```
 uvaver   - Time average a UV data set.
 wobs     - Save UV data to a random-groups UV FITS file.
 specplot - Plot time-averaged visibility spectra.
```

The operations performed by most Difmap commands are automatically applied to all the currently selected IFs, one after the other. Exceptions are certain plotting commands where it only makes sense to display data from one IF at a time. However such commands provide both a command-line argument to explicitly specify a start IF, as well the option to interactively step through sampled IFs, one at time. The relevant plot commands are:

```
 vplot   -  Display baseline visibility amplitudes and phases versus time.
 tplot   -  Display the time-sampling of each telescope.
 corplot -  Display accumulated self-calibration corrections.
 cpplot  -  Display observed and model closure phases.
```

Other plot commands separately display data from all IFs on the same plot. Edits in those commands are applied to the source IFs of the individual points selected for editing. Such plot commands include:

```
 radplot  -   Display visibility amplitude vs. UV radius.
 projplot -   Display visibility amplitude/phase vs. projected UV distance.
 uvplot   -   Display the sampling of the UV plane.
```

The only command that explicitly combines IFs is the 'invert' command. This is a command that is usually called for you by Difmap commands that require an up to date version of the latest residual map. The 'invert' command convolves all the residual UV data one IF at a time onto a single regular two dimensional grid of the UV plane, and then Fourier inverts the result to produce a residual map. Combining the data together in this fashion avoids the inter-IF bandwidth smearing that would otherwise occur if visibilities of the same baselines, taken at the same times but at different frequencies were simply averaged to a single point in the UV plane.

Given that Difmap maps are formed by combining all selected IFs, the model that is built up by 'clean' or 'modelfit', is a model that simultaneously represents the structure in all those IFs. This is clearly only a reasonable assumption if the actual structure being mapped doesn't change significantly over the frequency range covered by the selected IFs. The more general case is called multi-frequency synthesis, and is not catered for by Difmap. In such cases you should map each IF separately.

The end result of multi-IF mapping is a single clean map formed from
the combination of data from all IFs.

Note that the fact that the selected channels of each IF are averaged
to form psuedo-continuum IFs, currently procludes the spectral-line
bandwidth synthesis mode of continuum mapping.

PERTINENT COMMANDS AND FUNCTIONS.
---

nif   - Return the number of IFs in the current observation.
nchan - Return the number of channels per IF.

polarization

Overview of Difmap polarization mapping.

Mapping polarization data in Difmap.

Difmap has limited support for polarization mapping. The main limitation is that there is currently no way to combine two maps of different polarizations to form a percentage polarization map or other combinations. Such post-processing of images must be done in other programs such as AIPS. Also the only polarization calibration performed by Difmap is self-calibration. All absolute calibration must be performed outside of Difmap, say in AIPS.

While it is only possible to make a map of one polarization at a time in Difmap, self-calibration corrections and editing applied while making one map are always applied to all other polarizations. This is a necessary feature, designed to ensure that polarization calibration and consistent UV coverage over all polarizations is preserved. So, if self-calibration is required, all polarizations can simultaneously be self-calibrated while making a single map of the strongest polarization. The same is true of the scope of self-calibration corrections wrt spectral-line data.

The polarizations recorded in the originating UV FITS file can be displayed with the 'header' command.

If an observation is recorded with multiple polarizations, the 'select' command must be used to select the polarization to be processed. This selection affects what is displayed in all plotting commands, and forms the data upon which all processing is based until the 'select' command is again called upon to change the selection.

The selected polarization may either be one of these polarizations, or be the name of a polarization that can be derived from them.

The names of recognised polarizations are:

  I Q U V RR LL RL LR XX YY XY YX

The following is a list of polarizations that may be contructed from other polarizations:

Name	Derived from:	Derived as:
I	RR and LL	(RR + LL)/2
Q	RL and LR	(RL + LR)/2
U	RL and LR	i(LR - RL)/2

V	RR and LL	(RR - LL)/2

If you need to save one polarization map before making a second of a different polarization, you will have to save as a FITS file, for post-processing in another package, with the 'wmap' command.

spectral_line

An overview of the current spectral-line facilities.

Difmap can make maps from spectral-line FITS files, but a full set of spectral-line facilities has yet to be implemented.

Major features that have not yet been implemented.

A major omission is a command to write spectral-line map cubes. At the moment, each spectral-line map must be written to a separate FITS file, and then be combined externally (eg. by MCUBE in AIPS). I hope to do something about this in the near future.

How to make spectral-line maps in Difmap.

It is only possible to make a map of one aggregate of channels at a time. This isn't as bad as it sounds, as I will attempt to show in the following discussion.

1. Looking at visibility spectra.

   In order to determine which spectral line channels contain interesting features and thus which channels to map, the first thing to do is to make plots of visibility spectra. The 'specplot' command provides this facility. By default, this command shows individual spectra to each baseline in the observation. For each baseline it performs a vector average of the visibility spectrum over all integrations. This is the default mode of display. However, the specplot command also allows one to restrict the source of visibilities to specified time ranges, polarizations, UV ranges, or groups of baselines. One can plot mulitple spectra per page for different values of these selections, so for instance, one can see how a spectrum of a given baseline falls off with UV radius.

   Specplot is a complicated command, and further details of how to use it can be found in the on-line specplot help pages.

2. Selecting one or more channels to be mapped.

   The 'select' command allows one to average together one or more ranges of channels per IF. The resulting averages (one per IF) constitute the data that will thereafter be processed, until the 'select' command is again invoked to change the selection.

   For instance:

   0>select I, 10,20, 30,40

extracts the total intensity (I) over channels 10..20 and 30..40 and averages the results into a single psuedo channel, referred to as the current processing stream.

If the observation contains more than one IF, then channel numbers are assigned contiguously across all IFs. For example, if one has two IFs, containing 64 channels each, then channel numbers between 1 and 64 refer to channels of the first IF, and 65 to 128 refer to channels of the second IF. The same convention is used by the 'specplot' command. Note that this does not require that IFs be contiguous in frequency, or even that the interchannel frequency increment have the same sign in neighboring IFs. It is just a convenient way to specify IF-specific channel ranges without actually having to specify IF numbers. When doing spectral-line mapping the averaged channels are usually taken from a single IF. When this happens, the other IFs are unsampled and will not be displayed in any of the visibility plotting commands.

Note that channel averaging as described above precludes the possibility of bandwidth synthesis. Thus if the bandwidth enclosing the averaged channels is too wide, bandwidth smearing will result. Note that this is different from the way that multiple IFs are handled. Multiple IFs are kept apart, except during the gridding step of fourier inverting visibilities into the map plane.

3. Processing a selected stream.

Once the 'select' command has been used to average together a range of channels for processing, all difmap commands operate on the resulting psuedo channel, or processing stream. In particular all plot commands display just this stream. One may then make a map as though one were processing continuum data, using the 'clean', 'selfcal' and other commands to build up a model of the image plane representation of the data. See the cookbook for details on making continuum maps.

4. Selfcal calibrations.

A common practice in spectral-line work is to make a good map of one strong channel (or range of channels) and use the selfcal calibrations that were needed to produce that map, to calibrate the rest of the channels. In recognition of this fact difmap automatically applies selfcal calibrations identically to all channels (and polarizations), regardless of the selected data stream. This is an important feature. If instead, one were allowed to self-calibrate different channels separately, the relative positions of features in different channels would be lost.

A special case of the above technique is to map the background

continuum and use the calibrations needed to get a good continuum map as the basis for the spectral-line calibration. To do this, all you have to do is select the range of channels that contain just continuum data and map them, using selfcal wherever appropriate.

5. Editing.

   Editing is accomplished interactively with various plot commands. By default, although these commands only display visibilities of the selected stream, edits are applied equally across all spectral-line channels of all IFs. The plot commands provide toggleable options to change this default, such that edits can be applied just to the displayed IF and/or just to the spectral-line channels of the selected stream. The key bindings for these two toggles are 'I' and 'W' respectively. The 'I' toggle is not provided in commands which display all IFs simultaneously since edits are then always applied just to the IFs of the specified visibilities.

6. Continuum subtraction.

   Continuum subtraction in difmap exploits difference-mapping facilities to provide a more flexible scheme than is generally provided in other programs. To use it one must make a clean map of the continuum channels to build up a model of the continuum. Once this has been done the model can be installed as a background continuum model using the 'setcont' command. The UV representation of this model is then subtracted from the current and future processing streams, until deliberately discarded with the 'clrmod' command. Inportant advantages of this technique are that self-calibration is still applied to the unsubtracted data, that the continuum model can be incrementally improved by later additions with the 'setcont' command, and that the continuum model can even be removed with the 'clrmod' command when no longer required. For further details read the help information on the 'setcont' command.

7. Making a cube of maps.

   To produce multiple channel maps it is necessary to map each channel range separately. At the moment, the only way to save these maps is in separate FITS files, using multiple calls to the 'wmap' command. I hope to support map cubes in the future. To create a map cube, it is thus necessary to produce multiple map files and then combine them into a cube in another program, eg. MCUBE in AIPS.

   If you follow the scheme described above, where one psuedo channel is mapped in order to solve for self-calibration solutions for all channels, then all that is then required is a way to run the 'select', 'clean' and 'wmap' commands in a loop to produce multiple

channel maps. This can be done using difmap 'do' loops. For example:

```
  0>integer channel
  0>do channel=10,20,4
  1>  select I, channel, channel+3
  1>  clrmod true
  1>  clean 300,0.01
  1>  wmap `"map_" // strnum(channel) // ".fits"`
  1>end do
  0>
```

This would produce maps of channels 10..13, 14..17, and 18..21, and write them to fits files called: map_10.fits, map_14.fits and map_18.fits.

These maps could then be read into AIPS via a one-line loop on the AIPS command line, of the form:

```
  >for i=10 to 20 by 4;infile='dir:map_'!!char(i)!!'.fits';go fitld
   wait fitld; end
```

Where 'dir' is the name of an environment variable that you must define before running AIPS to point at the directory in which the files reside. The individual maps could then be combined into a cube via AIPS MCUBE.

The above Difmap loop is not very sophisticated and is just an example. A better example would include the addition of the mapplot command to allow interactive selection of clean windows. This in turn could be put in a nested loop along with the clean command (using a smaller number of clean iterations per loop), so that the clean windows could be adjusted during cleaning, as opposed to setting them once before cleaning each map plane.

The ` ` syntax in the above simply allows a string expression to be used where a literal string (one without enclosing ""s) is expected.

subarrays

A discussion of sub-array handling in Difmap.

Sub-arrays in Difmap.

CONTEXT

To increase the UV coverage and sensitivity of an experiment it is common to combine one or more observations from different times, telescope arrays, or different configurations of a single interferometer. In each case, the antennas in the different observations usually have to be calibrated separately, so the telescope arrays are treated as being different sub-arrays of a single hypothetical interferometer.

Difmap details.

Difmap does handle multiple sub-arrays if they all appear within a single input file, but it does not currently provide facilities for mergeing two or more UV FITS files to produce a multi-sub-array data-set. This should instead be done before entering Difmap, say with DBCON in AIPS (DOPOS(1,1) > 0; DOARRAY < 0).

Sub-arrays are actually effectively unrelated, so the visibilities for each sub-array must actually be separately processed. Most Difmap commands do this automatically, processing each sub-array one after the other. Exceptions to this rule are certain plot commands, along with a few sub-array manipulation and informational commands. In these cases, sub-arrays must be refered to by number. The association between sub-array numbers and arrays can be ascertained with the 'header' command.

Telescope specification strings.

Since a single telescope may appear in more than one sub-array, Difmap usually requires that when you name a telescope, baseline, or closure-triangle, that you also specify the number of the sub-array in which the telescope(s) belong. The only exception to this rule, is when the telescopes belong to the default sub-array, which is 1 if the specification is given on the command line to a command, or equal to the number of the sub-array that is currently being displayed when given interactively in a plot command. In these cases the sub-array index can be omitted. In particular, if the observation only has a single sub-array, then the default sub-array always refers to that sub-array.

The general form of all supported telescope specifications is:

```
 [sub-array-number:]telescope_name_a[-telescope_name_b[-telescope_name_c]]

Elements of the specification that are enclosed in [] are optional.

The actual number of telescope names expected depends upon whether a
telescope, baseline or closure-triangle specification is required by
the Difmap command. In each case, trailing telescope names can be
omitted. Usually when this is done the first recorded telescopes in
the sub-array that can be associated with the given telescope name(s),
are substituted. Alternatively, commands that accept more than one
type of telescope specification note whether a telescope, baseline or
complete closure-triangle specification is given and act accordingly.

Example telescope specifications are:

1. To specify an antenna called OVRO, in sub-array 1 the specification
   would be:

    1:ovro

2. To specify the baseline formed by telescopes named OVRO and WSRT in
   sub-array 1, the specification would be:

    1:ovro-wsrt

3. To specify the triangle formed by telescopes named OVRO, WSRT and
   BONN in sub-array 1, the specification would be:

    1:ovro-wsrt-bonn

Telescope names are matched using a case-insensitive min-match search
of all telescopes in the given sub-array. Thus if sub-array 2
contained telescopes named BONN and BOLOGNA, then:

  2:bon-bol

would be sufficient to select baseline BONN-BOLOGNA, whereas:

  2:bo-bol

would evoke an error message.

Note that the : separator after a sub-array specification is only
taken to denote such a separator if it is preceded by an integer at
the start of the specification. This makes it possible to select VLA
antenna names, which themselves contain a colon. Thus, if the default
sub-array is sub-array 1, then:

  1:vla:e8
```

```
and

  vla:e8

are both equally acceptable specifications for telescope VLA:E8 in
sub-array 1.

LIMITATIONS
-----------
At the moment all sub-arrays must all have been observed at the same
frequency and bandwidth. This translates to the requirement that each
sub-array be refered to by the same frequency ID in the input UV FITS
file. If this restriction proves to be a problem then I will endeavour
to impliment the more general case of allowing a separate FQID per
sub-array.

Since random-groups UV FITS files also impose the restriction that all
visibilities have the same number of frequency channels, polarizations
and IFs, removing the above restriction would not be as useful as it
might be, so I have not implemented it.

Sub-array specific commands and functions.
------------------------------------------

The command that provides the most general information on sub-arrays
is the 'header' command. This also shows other information about the
observation. Its limitation is the that it is given in textual form, so it
can not be used as an aid to writing scripts. The following functions
can be used to obtain a few bits of information about sub-arrays:

 nsub     -  Returns the number of sub-arrays in the data-set.

 nbase    -  Returns the number of baselines in a given sub-array.

 ntel     -  Returns the number of telescopes in a given sub-array.

 basename - Returns the name of the n'th baseline in a given sub-array.

 telname  - Returns the name of the n'th telescope in a giveb sub-array.

Plot commands that display data for one sub-array at a time include:

 tplot    - Plots the telescope versus time sampling of sub-arrays.

 vplot    - Displays visibilities of sub-array baselines.

 cpplot   - Display closure-phases of sub-array closure-triangles.

 corplot  - Display self-calibration telescope corrections.
```

```
 In these commands, capital N and P can be used to move to the Next or
 previous Sub-array in order of sub-array index. The 'T' key can also
 be used to select a given plot via a telescope specification string.

Plot commands that plot all sub-arrays at once, but allow one to
highlight a given telescope, include:

 radplot  - Display visibilities versus radial UV distance.

 projplot - Display visibilities versus projected UV distance.

 uvplot   - Display visibility sampling of the UV plane.

 Each of these commands responds to the 'T' key to allow the user to
 request that a given telescope be highlighted, via a telescope
 selection string.
```

Difmap commands and functions

The following pages show the contents of the help files of each difmap command and function. The same pages can be seen from whithin Difmap by typing:

help name_of_command_or_function

addcmp

```
Add a model component by hand to the tentative model.

  addcmp flux, vf, x, y, vxy, major, vm, ratio, vr, phi, vp, type

EXAMPLE
-------

 0>mapunits arcsec
 0>addcmp 0.1, false, 0, 0, true, 0.3, true, 0.5, true

The above adds a gaussian component of flux fixed at 0.1 Jy, positioned
at the center of the current map but allowed to move during model fitting,
having a major axis of 0.3 arcseconds FWHM and an axial ratio of 0.5
both of which are allowed to vary during model fitting, and an implicit
major axis position angle of 0 degrees.

PARAMETERS
----------
flux  -  The integrated flux of the component, measured in Jy.
vf    -  If TRUE allow the flux to vary during model fitting.

x     -  The relative X-axis position of the component centroid in the
         current map units. (See help mapunits).
y     -  The relative Y-axis position of the component centroid in the
         current map units. (See help mapunits).
vxy   -  If TRUE allow x and y to vary during model fitting.

major -  The FWHM major axis of the elliptical aspect of the component
         measured in map units (See help mapunits).
vm    -  If TRUE allow major to vary during model fitting.

ratio -  The ratio of the minor axis to the major axis (0 -> 1).
vr    -  If TRUE allow the axial ratio to vary during model fitting.

phi   -  The Position angle of the major axis (degrees North -> East).
vp    -  If TRUE allow phi to vary during model fitting.

type  -  The component type. The default if not given is to assume
         that the component is a delta function unless a non-zero
         major axis has been provided.
         Valid types include:

                0 - Delta function.
                1 - Gaussian.
                2 - Uniformly bright disk.
                3 - Optically thin sphere.
                4 - Ring.
```

CONTEXT

This command is provided mainly for use in automatic mapping scripts
where the normal interactive methods of adding model components (see
help mapplot and help edmodel) are inappropriate. In such contexts
this command can be used by a script to enter guesses at model
component characteristics and then use the modelfit command to
fit it to the data in order to parameterize maps after hands-off
mapping. Note that there are some restrictions on which parameters can
actually be fixed during modelfitting. These restrictions are silently
enforced by the modelfit command and you should acquaint yourself with
the modelfit help information before using this command seriously.

RELATED COMMANDS
----
mapplot - (In the sense that it can be used to interactively add components).
edmodel - Edit the current models in your favorite editor.
modelfit - Fit a variable image plane model to UV data.

addhist

```
Append a new line to the recorded history of an observation.

  addhist text

EXAMPLE
-------

 0>addhis "DIFMAP This is a new history line."
 0>

PARAMETERS
----------

text   -   The text of the new history line. This will be truncated to a
           maximum of 80 characters where necessary.

CONTEXT
-------
The only history information that difmap writes is a line to say when the
UV FITS file was read into difmap. If you wish to record more processing
history this command may be used to do it.

RELATED COMMANDS
----------------
showhist - Display the history recorded with the current observation.
clrhist  - Clear the history information recorded with the observation.
```

addwin

```
Append a new entry to the list of clean windows.

  addwin xa, xb, ya, yb

EXAMPLE
-------

0> addwin -1.5,1.0,-3.0,2
0>

PARAMETERS
----------

xa  -   The relative Right-Ascension of either edge of the new window.
xb  -   The relative Right-Ascension of the opposite edge to 'xa', of
        the new window.
ya  -   The relative Declination of either edge of the new window.
yb  -   The relative Declination of the opposite edge to 'ya', of the
        new window.

Coordinates should be specified with the same sign convention and
units as displayed in mapplot. (See help on the mapunits command).

CONTEXT
-------
Normally clean windows should be set with the cursor in the mapplot
command. Each new window added is appended to a list of clean windows
for use in clean. The addwin command provides a way to add windows
to the same list, but directly at the command line.

RELATED COMMANDS
----------------
mapplot - Allows adding and deleting windows with the cursor.
delwin  - Deletes all clean windows.
clean   - Cleans within the specified clean windows.
```

basename

```
Returns the name of baseline 'ibase' of sub-array 'isub'.

  basename ibase, isub

EXAMPLE
-------
Example 1  -  Print out all (nbase) baseline names in sub-array 1.

0>do i=1,nbase
1>  print basename(i)
1>end do
1:WSRT-BOLOGNA
1:WSRT-HSTK
1:BOLOGNA-HSTK
1:WSRT-VLBA_KP
1:BOLOGNA-VLBA_KP
1:HSTK-VLBA_KP
1:WSRT-VLBA_LA
1:BOLOGNA-VLBA_LA
1:HSTK-VLBA_LA
1:VLBA_KP-VLBA_LA
0>

Example 2  -  Print the name of the third baseline in sub-array 2.

0>print basename(3,2)
2:OVRO-WSRT

The "number:" prefix indicates the number of the sub-array to which the
baseline belongs.

PARAMETERS
----------
ibase  -  The number of the baseline who's name is required.

isub   -  Default: 1
          The number of the sub-array from which the baseline name
          is required.

RELATED FUNCTIONS
-----------------
nbase - Return the number of baselines in a given sub-array.
nsub  - Return the number of sub-arrays in an observation.
```

beamloc

Change when and where mapplot plots the clean beam ellipse.

```
  beamloc xcenter, ycenter, minsize, maxsize
```

EXAMPLE

```
  0>beamloc 1.0, 0.0, 0.5
  Mapplot clean beam ellipse center: 1,0. Max size: 0.5.

  0>beamloc -1
  Mapplot will not plot a clean beam ellipse.
```

PARAMETERS
----

xcenter - The location of the beam center along the X-axis, measured in normalized plot coordinates (0 -> 1). The initial default is 0.0, the left of the plot.

ycenter - The location of the beam center along the Y-axis, measured in normalized plot coordinates (0 -> 1). The initial default is 0.0, the bottom of the plot.

minsize - The minimum allowed fractional extent of the beam ellipse with respect to the plot width and height. The beam will not be plotted when its size is smaller than this limit. The initial default is 0.01.

maxsize - The maximum allowed fractional extent of the beam ellipse with respect to the plot width and height. The beam will not be plotted when its size exceeds this limit. The initial default is 0.3.

CONTEXT

When plotting clean maps, mapplot usually plots a filled ellipse representation of the clean beam in the bottom left corner of the map.

For esthetic and practical reasons, it is usually desireable to prevent the beam ellipse from being plotted when it is either very small with respect to the size of the plot, or so big that it comes to dominate or obscure important parts of the plot. The latter is particularly important when zooming in on fine detail. The 'minsize' and 'maxsize' arguments allow one to specify the allowable range of sizes as fractions of the width and height of the plot.

```
The position at which the center of the beam is plotted can also be
changed via the 'xcenter' and 'ycenter' arguments. Both positions are
specified in normalized plot coordinates, with 0,0 refering to the
bottom left corner and 1,1 refering to the top right corner. If either
'xcenter' or 'ycenter' lies outside the range 0 and 1, then no beam
will be drawn. Otherwise the beam will be positioned at the position
given, with the exception that if the position would place part of the
beam outside the map, it will be moved inwards, suitably spaced from
the edge.

RELATED COMMANDS
----------------
mapplot  -  Display map and beam images.
xyrange  -  Set the boundaries of the sub-image to be displayed in mapplot.
loglevs  -  Set logarithmic levels.
mapcolor -  Select mapplot colormap type and transfer function.
mapfunc  -  Change the transfer function used in mapplot.
```

clean

```
Clean a residual dirty map with the dirty beam.

  clean niter, gain, cutoff

EXAMPLE - (there is a more general example later in this help topic)
-------

0>clean 100,0.05,0.0
Inverting map and beam
Estimated beam: bmin=1.8350 mas, bmaj=6.1080 mas, bpa=27.4 degrees
Clean: niter=100  gain=0.05  cutoff=0
Component: 050  -  total flux cleaned = 3.218951 Jy
Component: 100  -  total flux cleaned = 4.508268 Jy
Total flux subtracted in 100 components = 4.508268 Jy
Clean residual min=-0.184183 max=0.394841 Jy/beam
Clean residual mean=0.024779 rms=0.092559 Jy/beam
0>

All but the first line are responses from 'invert' and 'clean'.

PARAMETERS
----------
niter  -  The Maximum number of CLEAN iterations to be attempted.
          If this is -ve then CLEANing will stop on the component
          before the first negative component.

gain   -  The CLEAN loop gain (normally 0 -> 1). This sets the fraction
          of the peak (absolute) residual that is subtracted on each
          CLEAN iteration. The choice of a gain is a trade-off between
          the ideal (as small as possible) and the speed at which the
          map is reduced to the noise. It is common to start with a few
          iterations at high clean gain - say 0.1 - to clean away any
          bright point-like features such as a Galaxy core, and then
          to reduce it to clean the lower surface brightness extended
          structures.

cutoff -  Cleaning will stop if the maximum absolute residual falls
          to this value or lower (Jy). This may be used to prevent
          CLEAN from cleaning below the flux level at which (due to
          artifacts or noise) structures in the residuals can be
          believed.

'clean' remembers the parameters that were given to it the previous time
it was invoked. Any omitted arguments will retain these values.

WINDOWS
-------
In addition to the above explicit command line parameters, CLEAN can
```

```
be supplied with a list of rectangular windows, such that CLEAN
components are only taken from within these windows. If no windows are
supplied then CLEAN will use the whole map. Clean windows can be set
directly via the 'mapwin' command or set with the cursor in the
'mapplot' command. The latter is the easiest to use.

The registration between map pixels and clean window edges is such
that all pixels who's centers lie inside the windows are used. Where
the window is so thin as to not enclose any pixel centers, the pixels
with the nearest centers are used. Windows may be set interactively
with the cursor (see help on the 'mapplot' command).

CONTEXT
-------
Clean takes the residual dirty map from the previous clean and
iteratively subtracts the dirty beam pattern convolved with the
loop-gain times the brightest residual pixel. The end result is a
new residual dirty map and a set of delta-function model components
representing the flux subtracted from the selected pixels.

Errors in the gains and phases at individual telescopes set the level
down to which it is safe to CLEAN. To enable further CLEANing it is
necessary to follow CLEAN by self-calibration, which compares the
observed visibilities to the CLEAN model to determines self-consistent
solutions to the telescope based gain and phase errors. Having done
this it should be possible to CLEAN to a lower residual flux than
before.

A typical mapping sequence is:

0> observe myfile.uvf  (Read the FITS UV-data file)
0> vplot               (edit the visibilities to remove bad points)
0> mapsize 256,0.5     (set the map grid and cell-size)
0> mapplot             (Display the dirty map and set CLEAN windows)
0> clean -100,0.1,0.2  (Clean up to 100 components at a gain of 0.2,
                        stopping before the first negative component or
                        when the peak residual is less than 0.1 Jy)
0> selfcal             (Apply phase-only self-cal)
0> mapplot             (Display corrected residuals and change the
                        clean windows if necessary)
0> clean 100,0.05,0.05 (Use a lower clean gain and allow negatives,
                        while cleaning down to a lower residual flux)
0> selfcal true,true,900  (Amplitude+phase self-cal)
0> vplot               (Edit discrepant points - compare with model)
0> mapplot
0> clean

etc.. until the residual flux won't further decrease or the self-cal
fit starts to diverge.
```

```
0> mapplot cln          (Look at the clean map)
0> save mynewfile       (Save the UV data, the map, the model, the
                         clean windows and the difmap parameters)
0> exit                 (Finished)
```

SIDE EFFECTS

If the beam and/or residual map need to be re-calculated following data editing, re-weighting etc.. then 'clean' will call 'invert'.

LIMITATIONS

Clean only cleans the inner half of the actual map array that is allocated. (mapplot only displays this area when plotting the map). Thus 'mapsize 256,0.5' will result in a map area 128x128 pixels wide.

RELATED COMMANDS
---

selfcal - Uses the clean model in self-calibration.
gscal - Uses the clean model and self-calibration to find overall gain corrections for each telescope.
invert - Converts residual UV data to the residual dirty map.
restore - Generate the clean map.
vplot - Interactive display and editing of visibilities.
mapplot - Display residual or clean map, or dirty beam.

clrhist

Clear the history information recorded with the observation.

```
  clrhist
```

EXAMLE

```
0> clrhist
```

CONTEXT

It is normal for UV FITS files to contain an extensive processing history, such as that recorded by AIPS. While Difmap adds very little to this Difmap does preserve it and passes it on to output UV FITS and map image FITS files, and while in some cases it might be useful, in others it may significantly enlarge data files for no good reason.

The 'clrhist' command clears the currently recorded history.

RELATED COMMANDS
----

addhist - Add a new line of history.
showhist - Display the currently recorded history.

clrmod

```
Clear one or more of the established, tentative and continuum models.

  clrmod doold, donew, docont

EXAMPLES
--------

0>clrmod
clrmod: Cleared the tentative model.
0>

0>clrmod true
clrmod: Cleared the established and tentative models.
0>

0>clrmod true,true,true
clrmod: Cleared the established, tentative and continuum models.
0>

PARAMETER
---------
doold   -  Default=false
           If specified as true, then the established model will be cleared.

donew   -  Default=true
           If this argument is omitted, or explicitly specified as
           true, then the tentative model will be cleared.

docont  -  Default=false
           If specified as true, then the continuum model will be cleared.

CONTEXT
-------
In difmap the term 'model' refers to a mixed list of delta, gaussian
and other simple components, which when superposed in the image plane,
form a facsimile of the source being mapped. This model is split into
three parts, an established model, a tentative model and a continuum
model. The function of the 'clrmod' command is to clear one or more of
these models.

When the 'clrmod' command is invoked with no arguments, it clears just
the tentative model. This is most useful to discard the latest results
of the 'clean' command, after cleaning too deeply.

When the 'clrmod' command is invoked as 'clrmod true', it deletes both
the established and tentative model, but leaves any existing continuum
model untouched. This is commonly invoked after the 'select' command
has been used to select a new data stream, when which the model for the
```

```
previous selection is a bad match to the new selection.

For more information about models type 'help models'.
```

clroff

```
Undo all resoff calibration-offsets applied during this difmap session.

  clroff


CONTEXT
-------
If you have cold-feet about having used resoff to make your model
and observed data look better, clroff will remove the resoff
corrections.
```

corplot

```
Display accumulated telescope based self-cal corrections versus UT.

  corplot tel_name, IF_index

EXAMPLES
--------
1. Display the corrections for the BONN telescope in sub-array 1.

   0>corplot BONN

2. Display corrections for telescope 3 in sub-array 1.

   0>corplot `telname(3)`

3. Display corrections interactively for any telescopes.

   0>corplot

4. Display a telescope from sub-array 2, and its corrections in IF 3.

   0>corplot 2:BOLOGNA, 3

PARAMETER
---------
tel_name  -  Optional - default="".
             A telescope name specification. In interactive mode this
             specifies the first telescope to be plotted. When
             plotting to a non-interactive device it specifies a range
             of telescopes to be displayed. See the antenna_names help
             topic for a description of the syntax and meaning of
             valid telescope specification arguments.

IF_index  -  Default = The first sampled IF.
             The index of the IF to start displaying from. One may
             also move between IFs with the '[' and ']' keys - see
             below.

CONTEXT
-------
This command gives one the opportunity to see what corrections
have been applied by selfcal and which integrations couldn't be
corrected due to lack of data. It also gives you the opportunity to
flag or unflag corrections, and to reset indivudual corrections.

Flagged corrections are plotted in blue. Good corrections are plotted
in green. Each page shows the corrections of a single telescope from a
single sub-array, in a given IF.
```

INTERACTIVE MODE

If the plot device has a cursor, then an interactive mode will be invoked. In this mode, initially corrections for the first telescope of the observation, or the requested telescope, will be displayed. Thereafter keyboard keys, in conjunction with the cursor allow one to peruse the corrections of other telescopes in any order.

To get a list of the currently defined keys and what they do, place the cursor within the plot window and then hit the 'H' key on the keyboard.

EDITING

Unless the selfflag command has been used to suppress flagging, the selfcal comand automatically flags corrections that it has insufficient information to determine. These flags can either all be removed with the 'uncalib' command, or toggled individually in 'corplot'. To toggle the flag status of a correction in corplot, click the left-mouse-button, or keyboard key 'A' near the point that you wish to flag or unflag. The flags will be applied both to the correction, and to all visibilities affected by that correction.

RELATED COMMANDS
---

scangap - Change the time gap used to delimit neighboring scans.
uncalib - Remove selected parts of corrections.
radplot - Display visibility amplitude vs. UV radius.
projplot - Display visibility amplitude/phase vs. projected UV distance.
uvplot - Display the sampling of the UV plane.
vplot - Display observed and model visibilities.
tplot - Display the time-sampling of each telescope.
cpplot - Display observed and model closure phases interactively.

cpplot

```
Interactive display and editing of observed and model closure phases.

  cpplot triangle, nplot, IF_index, npage

EXAMPLE
-------

1. Plot closure phases of triangles of telescope WSRT, using 10 plots
   per page.

   0>cpplot 10, wsrt
   Using default options string "efbm"
   For help move the cursor into the plot window and press 'H'.
   0>

PARAMETERS
----------
nplot     -  (Default = 5 plots per page).
             The maximum number of plots per page. The actual number
             of plots per page used will be restricted to the number
             of possible triangles that depend on the telescopes
             described in the 'triangle' argument.

triangle  -  (Default = "")
             A triangle specification comprised of an optional sub-array
             index plus colon, followed by between one and three telescope
             names each separated by a hyphen. Read the antenna_names
             help topic for more details

             1. If only one telescope is given, then all independent
                closure triangles with that telescope will be displayed
                at 'nplot' plots per page. There are up to
                ntel*(ntel-1)/2 - (ntel - 1) of these.

             2. If two telescopes are given then all independent
                closure triangles with the resulting baseline are
                plotted at 'nplot' plots per page. There are up to
                ntel-2 of these.

             3. If three telescopes are provided then this completely
                defines a single triangle to be plotted. Thus only one
                plot per page will be displayed.

IF_index  -  (Optional) Default = The first sampled IF.
             The index of the IF to start plotting visibilities from.

npage     -  (Optional) Default = 0 (with requests no page limit).
             The maximum number of pages to plot when plotting to
```

a non-interactive device.

CONTEXT

In the absence of noise and correlator errors, the only remaining sources of measurement errors, are at the individual telescopes. In terms of phases, where the absolute phase at any telescope is irrelevant, there are thus only N-1 telescope based phase errors compared to N(N-1)/2 baseline visibility measurements. There are thus N(N-1)/2 - (N-1) phase quantities that are un-corrupted by telescope based phase errors. Such quantities can be formed by summing visibility phases around a closed loop of three telescopes to cancel out telescope phase errors, and are known as closure phases.

Closure phases are thus independent of the phase errors caused by local atmospheric fluctuations over individual telescopes. They are also independent of phase-center position errors, because such errors translate to antenna dependant time-variable phase shifts.

In reality, noise, mismatched telescope bandpasses, correlator errors and limited precision mean that closure phases are less than perfect, but they are often still useful indicators of source structure if telescope based errors dominate visibility phases.

Closure phase is implicitly used in self-calibration to solve for and remove telescope based phase errors. This command may be profitably used to determine whether the closure phases are sufficiently well behaved that phase self-cal is possible.

CONFIGURATION VARIABLES
----

vflags - This is a string variable (shared with vplot) that over-rides the default display attributes. It is particularly useful when displaying to a hard-copy device, where interactive changes to the default attributes can not be made.

By default vflags="". In this case cpplot substitutes the equivalent of vflags="efmb", which means plot error bars, flagged data, the model, and break the plot into scans.

When vflags is not "", all toggled attributes are initially set to off, and the contents of the vflags string determine which of the attributes get turned back on.

HARD COPY MODE

If this command is invoked when the PGPLOT output device is a hard-copy device, such as a laser printer, then all triangles

corresponding to the given triangle specification will be plotted.
For example:

```
 0>dev /ps
 Attempting to open device: '/ps'
 0>cpplot 5,ovro
 Using default options string "efbm"
 Page 01: Triangles of 1:OVRO
 Page 02: Triangles of 1:OVRO
 Page 03: Triangles of 1:OVRO
 Page 04: Triangles of 1:OVRO
 Page 05: Triangles of 1:OVRO
 Page 06: Triangles of 1:OVRO
 Page 07: Triangles of 1:OVRO
 Page 08: Triangles of 1:OVRO
 Page 09: Triangles of 1:OVRO
 0>
```

This plotted all closure triangles of OVRO at 5 plots per page.

INTERACTIVE MODE

If the display device has a cursor, then an interactive session will be invoked. In this mode, one page of baselines is initially plotted and mouse-keys and keyboard keys are used to guide the command through plotting and data editing.

Once cpplot has been invoked, move the cursor into the display window and press the 'H' key on your keyboard. Whenever this is pressed during the cpplot session a list of key bindings will be displayed in the window from which cpplot was invoked.

Most keys are not case-sensitive, such that both 'H' and 'h' have the same effect.

On standard PGPLOT conforming devices with a mouse or other cursor control device, mouse buttons are equivalent to the following keyboard keys:

```
Left button   = 'A'   (This is the normal key for selecting positions).
Middle button = 'D'   (This is used to cancel incomplete select ranges).
Right button  = 'X'   (Use this to exit cpplot).
```

Note that on a windowing system, the cursor must be within the display window before pressing a keyboard key or mouse button will be noticed. However, after pressing a key that needs more complex answers, such as the entry of the number of baselines to display or the entry of a new triangle specification, the cursor should be moved to the original text window where a prompt will be displayed to read your selection.

```
MOVING ABOUT BETWEEN TRIANGLES
------------------------------

 N - Display next set of triangles.
 P - Display preceding set of triangles.

Pressing 'N' in cpplot causes the Next set of closure triangles that
match the last triangle specification, to be plotted on a new page. The
'P' key works identically but shows the Previous set of triangles.

 T - Specify a new triangle specification from the keyboard (text screen)

When you press this, a prompt will be displayed on the text screen and
you will be expected to enter a new triangle description using the
same format as described above for the 'triangle' command-line
argument. See the antenna_names help topic for a description of
triangle specification arguments.

MOVING BETWEEN IFs
------------------
Visibilities are only displayed from one IF at a time. The identity of
this IF is displayed above the collection of plots. To move onto the
next or previous IF in which any channels were selected with the
'select' command, use the following keys:

 ] - Move to the next sampled IF.
 [ - Move to the previous sampled IF.

The title above the plots will change to indicate which IF is being
displayed.

CHANGING HOW CLOSURE PHASES ARE DISPLAYED
-----------------------------------------
The following keys toggle attributes on or off. The display will
not be re-plotted immediately whenever one of these is toggled, so
you can press a sequence of toggle keys before re-displaying with
the new attributes. When the sequence is complete, simply press
any key that is not in the list below, such as the RETURN key
and the display will be updated with the new attributes.

 M - Toggle display of model visibilities
 F - Toggle display of flagged visibilities
 E - Toggle display of error bars
 B - Toggle breaking the plot into scans (where present)

By default, a scan is taken to be any set of integrations which is
separated by more than an hour from its nearest neighbors. This can be
changed with the 'scangap' command.
```

CHANGING THE NUMBER OF PLOTS PER PAGE.

S - Select number of sub-plots per page

You will be prompted for a number on the text screen. Your answer will be used to change the number of plots that appear per page on the screen.

CHANGING THE DISPLAYED UT RANGE

U - select UT range to be displayed (hit U twice for full range)

Press 'U' to request a change in the displayed UT range. You will then be expected either to press 'U' again to display the whole UT range, or to move the cursor to the start UT of the required range and press 'A' (left mouse button), then move the cursor to the end UT of the required range and press 'A' again. The plot will then be re-displayed over the new range and all subsequent plots will be displayed over this range. At any point before the UT range selection has been completed, pressing the 'D' key (middle mouse button) will quietly abort the selection.

CHANGING THE DISPLAYED CLOSURE-PHASE RANGE

Z - Select closure-phase range to be displayed (hit Z twice for full range)

Press 'Z' to zoom in on a selected closure-phase range. (Press it twice to revert to the full -180 to 180 degree range). You will then be expected either to press 'Z' again to display the whole closure-phase range, or to move the cursor to the first (top or bottom) closure-phase of the required vertical range and press 'A' (left mouse button), then move the cursor up or down to the end closure-phase of the required range and press 'A' again. The plot will then be re-displayed over the new range and all subsequent plots will be displayed over this range. At any point before the closure-phase range selection has been completed, pressing the 'D' key (middle mouse button) will quietly abort the selection.

CHANGING WHETHER REDUNDANT BASELINES ARE DISPLAYED

By default, for each reference telescope specification (eg. each reference baseline or telescope) that it plots triangles for, cpplot displays all unique triangles that include that spec. This is easy to understand and helps to highlight errors that are specific to the reference specification. However, it does result in you seeing each triangle more than once if you step through all reference specifications of a given type. This can be annoying if you have a

very large number of triangles. For this reason cpplot also provides the option to only show each triangle once, by only showing triangles with telescopes that are in increasing sequential order with respect to the last antenna of the reference specification. Thus if your reference specification is a baseline, the final telescope is only allowed to be taken from the set of telescopes that follow the last telescope of the reference baseline, in the list of all telescopes.

  0 - Toggle telescope ordering to only show non-redundant triangles.

EDITING DATA

Cpplot gives you the option to edit closure phases interactively. You can edit visibilities of a specific station, a specific baseline, or all three baselines of a selected triangle.

When displayed, flagged data appear as red '+' symbols, un-flagged data as green points and the model appears as a continuous light-blue line. In addition, if a visibility is flagged by a selfcal correction flag, but not by a normal visibility flag, it is displayed as a blue 'x' symbol.

Station editing:

 If you wish edits to be applied to all visibilities of a specific
 station have cpplot display closure phases for just that station.
 This is done by specifying just that station name when you invoke
 cpplot, or via the 'T' key. The rational behind this is that if a
 single station is responsible for closure phase errors (surprisingly
 this IS possible) you will probably only see this when plotting many
 closure triangles of that station.

Baseline editing:

 If you wish edits to be only applied to visibilities of a specific
 baseline, have cpplot display closure phases for just that baseline.
 This is done by specifying just that baseline name when you invoke
 cpplot, or via the 'T' key. The rational behind this is that if a
 single baseline is responsible for closure phase errors, you will
 probably only see this when simultaneously plotting many closure
 triangles of that baseline.

Triangle editing:

 If you ask cpplot to plot closure phases of a single triangle, then
 all edits are applied to each of the three baselines that make up the
 triangle. This mode of editing can also be selected when displaying
 closure phases of a specific station or baseline, by toggling between
 the default editing mode and triangle editing with the space bar.

' ' - (SPACE BAR) Toggles to and from triangle based editing.
When this toggle is active, the mode title above the plot will change between "Triangle editing..." and the default editing mode.

Note that cpplot displays a closure phase as flagged if any of the three visibilities that form it are flagged. Thus if you try to restore a flagged closure phase in baseline editing mode, then the closure phase will not appear to change state unless only that baseline was flagged.

It is also possible to further specify the scope of edits.

I - Toggle IF editing scope.
W - Toggle spectral-line editing scope.

By default, edits are applied to all polarizations, spectral-line channels and IFs related to the selected visibility. To specify that edits only be applied to the displayed IF, press the 'I' key. To specify that edits be only applied to the channels that were specified with the 'select' command, press the 'W' key. The mode line above the collection of plots, describes which of these editing modes is in effect.

A - Flag or unflag the nearest closure sample to the cursor.
(Left mouse button)

Pressing 'A' on the keyboard or the left mouse button near a displayed closure sample causes the status of the visibilities of that closure triangle to from un-flagged to flagged or vice versa. If flagged data are displayed, then toggling an un-flagged closure-phase will produce a red cross signifying its new flagged status. Otherwise the point will magically disappear, but can be seen subsequently if the display of flagged data is enabled.

C - Flag all data inside select box
R - Restore data inside select box

If you wish to flag or un-flag an extended region of data, point by point editing is tedious. The Clip and Restore keys, 'C 'and 'R' enable you to edit all points inside a square box selected with the cursor. To use this facility, press the respective key and then move the cursor to one corner of the required region and press 'A' (left mouse button). Then move the cursor to the opposite corner of the required region and again press 'A'. The selected points will be re-displayed with their changed statuses.

ENDING A CPPLOT SESSION

```
To end a cpplot session, press 'X' or the right mouse button.
If substantial editing was performed in cpplot then it is advisable to
use the wmerge command to save the modified file before continuing
to map the data.

RELATED COMMANDS
----------------
scangap  -   Change the time gap used to delimit neighboring scans.
radplot  -   Display visibility amplitude vs. UV radius.
projplot -   Display visibility amplitude/phase vs. projected UV distance.
uvplot   -   Display the sampling of the UV plane.
vplot    -   Display observed and model visibilities.
tplot    -   Display the time-sampling of each telescope.
corplot  -   Display accumulated self-calibration corrections.
```

delwin

```
Delete all clean windows.

  delwin

EXAMPLE
-------

0> delwin
All clean windows deleted
0>

CONTEXT
-------
Presently, the only way to delete specific clean windows is in mapplot.
Delwin provides an alternate way to remove all windows without having
to run mapplot.

RELATED COMMANDS
----------------
mapplot - Allows interactive adding and deletion of clean windows.
addwin  - Allows command line addition of windows.
wwins   - Save CLEAN windows to a text file.
```

edmodel

Modify the established and tentative models with an external editor.

```
  edmodel dovar
```

EXAMPLE

To edit all components of the established and tentative models type:

```
 0>edmod
[... After exiting the editor]
 A total of 2 model components were read from file edmod.scr
 0>
```

The following demonstrates what happens if you inadvertantly introduce a syntax error into the model file while editing:

```
 0>edmod
 rmodel: Error at field 2 on line 3 of file: edmod.scr
 0>
```

To only edit model components with variable parameters:

```
 0>edmod true
 Partitioning the model into established and variable parts.
 Adding 1 model components to the UV plane model.
 The fixed established model contains 1 components (1.38117 Jy).
 The variable part of the model contains 1 components (2 Jy).
 A total of 3 model components were read from file edmod.scr
 0>
```

PARAMETERS
----

dovar - Default = false
If this argument is omitted or given as FALSE, then all all components of the tentative and established models will be presented to be edited. Alternatively, if it is given as TRUE, then only those components that have at least one component marked as variable will be presented.

CONTEXT

During model fitting the edmodel command can be used to add,delete or change the components of the established and tentative models using an external editor. This is usually used to change values of component parameters or to change which parameters are to be held constant.

Note that a 'v' post-fixed to a parameter makes it a free-variable for model fitting. Unfortunately, since the coordinate system used to fit the components to the data is not the same as that displayed in model files it is not possible to fix many of the parameters individually. The following collective sets of parameters may be constrained or allowed to vary:

1. The absence or presence of a postfixed 'v' on the Flux parameter effects only the Flux parameter.

2. Placing a 'v' on either or both Radius and Theta implies that both are variable. It is not possible to individually fix them.

3. If the axial ratio is exactly 1.0 and there is only a 'v' postfixed to the Major axis parameter, then axial-ratio and phi will remain fixed during model fitting.

4. In general if the axial ratio is not exactly 1.0 then postfixing a 'v' to any of Major,Ratio or Phi, implies that they are all variable.

DEFAULT EDITOR

On UNIX systems the edmodel command defaults to invoking the UNIX 'vi' editor. If this is not the editor that you are used to, then you should override the default by assigning the EDITOR environment variable with the path of your editor. This must be done before entering difmap, preferably in your .cshrc or .login files.

At the shell level or in your .cshrc or .login files you would type one of the following lines to set emacs as your default editor:

Under Bourne compatible shells (eg. sh, bash, ksh):

```
EDITOR="emacs";export EDITOR
```

Under csh compatible shells (eg. csh, tcsh):

```
setenv EDITOR emacs
```

DETAILS

If 'dovar' is omitted or presented as FALSE, then the established model is first merged with the tentative model, then the tentative model is written to a temporary file, presented to your editor and on exit from the editor, read back into the tentative model. Since the established model is cleared by this operation, the next operation that requires a UV representation of the model will establish the model first.

If 'dovar' is given as TRUE, then Edmod first partitions the established and tentative models into two parts, a model established in the UV plane (this can take significant time), formed only from fixed components, and a tentative variable model to be edited. It then writes the variable components of the model into a scratch file and invokes an external screen editor on it. When the user exits from the editor, the scratch file is read and deleted. If no errors were found in the file then the edited model supersedes the original tentative model.

RELATED COMMANDS
---

modelfit - Fit model components to UV data.

get

```
Restore UV data, models and windows from files.

  get prefix_name

EXAMPLE
-------

0>get 3c345
Attempting to open FITS file: 3c345.uvf
... details of UV FITS file contents
A total of 94 model components were read from file 3c345.mod
rwins: Read 3 windows from 3c345.win
0>

PARAMETERS
----------

prefix_name  -  All the required files must have this as there prefix
                followed by the standard suffixes listed below.

STANDARD SUFFIXES
-----------------

To the prefix name that you enter the following extensions are
appended to indicate the file type:

 .uvf  -  The suffix of the UV-FITS data file.
 .mod  -  The suffix of any model file.
 .win  -  The suffix of any windows file.

CONTEXT
-------
Before leaving difmap it is important to save all processed data
unless the data is to be discarded. The 'save' command provides a
convenient method for saving all relevant data with a single command.

The 'get' command provides the matching facility for reading the
files back into difmap.

Note that it doesn't read the FITS restored map file.

IMPORTANT
---------
The get command does not restore the running parameters (such as the
UV weighting and map size) to the states that they held when the save
command was called - it only restores the data files. To do this don't
use the 'get' command directly. Instead execute the .par file command
file that was produced with the save command (in the above example
```

```
this file would be called 3c345.par). This file contains all the
commands necessary to restore both the data files and the state of all
running parameters. See help on the 'save' command for more details.

RELATED COMMANDS
----------------
save   - Save UV data, models, windows, the restored map and a command
         file to use to restore the running parameters.
rwins  - Read previously saved CLEAN windows from a text file.
rmodel - Read a CLEAN model from a VLBI model file.
```

gscale

```
Self calibrate to determine overall telescope amplitude corrections.

  gscale dofloat

EXAMPLES
-------

0>gscale
Computing UV representation of latest clean model (147 components)
The established model now contains 147 components and 7.0511 Jy
Performing overall amplitude self-cal

Correcting IF 1.
 Amplitude normalization factor in sub-array 1: 1.01723
 Telescope amplitude corrections in sub-array 1:
  BONN      0.97     WSRT      0.95     JBNK1     0.99     BOLOGNA   1.01
  TORUN     1.00*    HART      1.01     HSTK      1.01     NRAO      1.02
  VLBA_KP   0.96     VLBA_PT   1.00*    VLBA_LA   0.96     VLA27     0.98
  OVRO      0.96
 Fit before self-cal, rms=0.498946Jy  sigma=3.396564
 Fit after  self-cal, rms=0.438911Jy  sigma=3.160276

Reinstating the default IF.
0>

All but the first line are responses from the 'gscal' command.
Some of the reported corrections are post-fixed with a '*' symbol.
This means that no solution was possible for that telescope.
These corrections are not 1.0, only because of amplitude
normalization.

Without amplitude normalization (dofloat=true) the same data-set gave:

0>gscale true
Performing overall amplitude self-cal

Correcting IF 1.
 Telescope amplitude corrections:
  BONN      0.97     WSRT      0.95     JBNK1     0.98     BOLOGNA   1.01
  TORUN     1.00*    HART      1.02     HSTK      1.02     NRAO      1.01
  VLBA_KP   0.96     VLBA_PT   1.00*    VLBA_LA   0.96     VLA27     0.98
  OVRO      0.96
 Fit before self-cal, rms=0.500856Jy  sigma=3.412605
 Fit after  self-cal, rms=0.365222Jy  sigma=2.861346

Reinstating the default IF.
0>
```

```
PARAMETER
---------
dofloat - If this parameter is omitted or given as false, the
          telescope corrections are normalized to maintain the current
          total flux. Alternatively, if dofloat=true then the
          telescope amplitudes will be allowed to float and the
          observed flux may be changed if not sufficiently
          constrained.

CONTEXT
-------
When one or more telescopes are miscalibrated by a constant factor,
this command may be used to solve for the correct telescope
amplitudes. In order to do this a reasonable model of the source
structure must have been provided. Such a model may be provided using
CLEAN or using a model from the VLBI modelfit program read into this
program via the 'rmodel' command.

This command should be used with caution. For instance, comparison of
the current model, in 'vplot', and the observed visibilities may
appear to indicate a number of consistently high baselines. This often
indicates data that hasn't been cleaned deeply enough. In particular,
check to see if just the shortest baselines are too high by examining
the plot of visibility amplitude verus UV radius given by the radplot
command. Such missing flux implies the existence of un-cleaned low
surface brightness extended emission that hasn't been cleaned yet. Try
switching to natural weighting (see help uvweight) and/or apply a
UV-taper before cleaning (see help uvtaper). This may reveal such
emission, which may then be cleaned.

If it turns out that artifacts due to poor amplitude calibration,
prevent you from cleaning low surface-brightness extended emission
then you should use the selftaper command to weight down the
significance of the short baseline visibilities before calling gscale
(see help selftaper). Failure to do this will make gscale attempt to
force the visibility data to fit the incomplete model at short UV
radii.

Amplitude self-calibration relies implicitly on the existence of
closure amplitudes. To form such a closure amplitude requires that
there be un-flagged visibilities on that lie baselines in closed
arrays of at least 4 telescopes. Gscale attempts to detect
visibilities that do not satisfy these conditions and exclude them
from the fit. How it does this, and whether these visibilities are
then flagged, is controlled by the selfflag command. See help selfflag
for more details.

NB. Observations that contain multiple sub-arrays and/or multiple IFs
    will produce nif * nsub lists of telescope corrections, instead of
```

```
    the single list given the examples above.

RELATED COMMANDS
----------------
selfflag - Used to control the fate of un-correctable data.
selfcal  - General self-calibration command.
selftaper - Used to down-weight short baselines during selfcal.
selflims  - Used to set limits to amp and phase corrections in selfcal.
startmod  - Phase selfcal to a starting model then discard the model.
```

header

List useful parts of the observation header on one's terminal.

```
header
```

imstat

```
Return image plane map statistics.

  imstat statistic

EXAMPLE
-------

 0>print imstat(rms), imstat(mean), imstat(noise)
 0.237115 0.00853315 0.0056867
 0>
 0>print imstat(bmin),imstat(bmaj),imstat(bpa)
 2.62014 20.9194 -10.0713
 0>

PARAMETERS
----------

statistic  -  The name of the statistic wanted. Recognised names are:

               rms   -   The RMS flux density in the map (Jy/beam).
               mean  -   The mean flux density in the map (Jy/beam).
               noise -   The noise level in the map estimated from the
                         visibility and gridding weights. (Jy/beam).
                         Note that this number is meaningless unless
                         the visibility weights are the reciprocal of
                         the amplitude variance. See help wtscale for
                         details.
               bmin  -   The minor axis FWHM of the beam size
                         estimated from the data during the last
                         invert (map units, see help mapunits).
               bmaj  -   The major axis FWHM of the beam size
                         estimated from the data during the last
                         invert (map units, see help mapunits).
               bpa   -   The position angle of the beam major axis,
                         estimated from the data during the last
                         invert (degrees North -> East).

CONTEXT
-------
This function provides access to statistics relating to the latest
map. The return value may be used in expressions, and may thus be used
in automatic mapping procedures.

SIDE EFFECTS
------------
The map will be re-inverted if not currently up to date.

RELATED COMMANDS
```

```
----------------
uvstat   - Return UV plane visibility statistics.
peak     - Return details of the min,max or absolute max flux in a map.
mapvalue - Return the value of the map pixel nearest to a given coordinate.
```

invert

```
Grid selected UV data and Fourier invert it to a (residual) dirty map

  invert

EXAMPLE 1
---------

 0>invert
 Inverting map and beam
 Estimated beam: bmin=0.7503 mas, bmaj=1.8830 mas, bpa=-10.9 degrees
 0>

The two lines without prompts are the response from the invert command.
The second of these is an estimate of the restoring beam size.

EXAMPLE 2
---------

 0>mapsize 256,2
 0>invert
 Inverting map and beam
 Your choice of large map pixels excluded 49.3% of the data.
  The x-axis pixel size should ideally be below 1.025 milli-arcsec
  The y-axis pixel size should ideally be below 3.466 milli-arcsec
 Estimated beam: bmin=9.189 mas, bmaj=23.87 mas, bpa=-11.54 degrees
 Estimated noise=6.17991 mJy/beam.
 0>

In this case 49% of the visibilities represented higher spatial
frequencies than could be Nyquist sampled by the coarse pixel spacing
of the chosen map grid. These visibilities were thus excluded from the
map produced by invert. The third and fourth lines of output show the
maximum pixel spacings that can be accomodated in RA and Dec without
lossing data. One could satisfy both sizes by using the mapsize
command to select a new square map pixel size of 1 arcsecond, or by
using the mapsize command to select a rectangular pixel size of
1.0 x 3.0 arcseconds.

CONTEXT
-------
Invert is the command that takes UV data and transforms it to a dirty map
and a dirty beam. Normally 'invert' is run for you by any commands that
operate on the residual map, such as:

clean   - CLEAN a residual map.
restore - Restore a residual map.
mapplot - Display a residual map or beam.
```

It is only run by these commands when the current dirty map and/or beam has been invalidated by modifications to the UV data. The beam often doesn't need to be recomputed under these circumstances. When it does need to be re-computed then 'invert' will also report a corresponding estimate of the new beam dimensions.

RESIDUALS

If an established clean model exists then this will be subtracted from the observed visibilities while gridding. The result is to produce a dirty residual map approximately the same as the one left after clean, but devoid of any aliasing from the removed components. If a non-residual dirty map is desired, then discard the established clean model by typing 'clrmod true' and re-invert.

RUNNING PARAMETERS

Although the command itself takes no arguments, the procedure that it runs takes a number of parameters. These are set and changed through a number of related difmap commands. Reasonable defaults are set for most of these, but you will be required to at least read a UV data file, using the 'observe' command and to specify a map grid, via the 'mapsize' command before first using invert. The rest of the commands offer a choice of visibility weighting and selection schemes which effect how the data are gridded on the UV plane. These commands are listed in the RELATED COMMANDS section below, and each command is discussed separately in its own help file.

GRIDDING

Visibilities for each IF of an observation are combined in the UV plane during gridding. If each IF has a different frequency then this implements a crude form of multi-frequency-synthesis, however currently no provision is made to correct for spectral-index effects, so if you don't think that the source structure and flux are constant between the multiple frequencies then you are advised to split the IFs in AIPS and map them separately.

Also note that if a range of spectral-line channels is selected via the difmap 'select' command, that a vector average of visibilities over those channels is formed before gridding. Thus different channels are not gridded separately and if the UV coordinates of visibilities change appreciably over the selected range them some degree of bandwidth smearing will be apparent.

UV SAMPLING CONSTRAINTS

In order to avoid aliasing and to avoid undersampling the image plane, the UV grid must be no more than half filled along either the U or the

```
V axes. If the current map cell-size is too large to accomodate the
range of U or V coordinates along the respective axes of the UV grid,
then 'invert' will exclude visibilities that lie outside the Nyquist
UV limits from the final map. The accompanying warning messages
provide directions for remedying this situation with the mapsize
command. Note that these are no more than warnings. There are times
when using large pixels is the only practicle way to view a large
enough field.

If the Nyquist limits are exceeded along both the RA (x) axis and the
Dec (y) axis, then the invert command will report corresponding
limiting pixel sizes for the two axes separately. In such cases you
could either take the smallest of the reported sizes and use the
mapsize command to select square pixels, or you could use the mapsize
command to select rectangular pixels to match both constraints. See
'help mapsize' for details.

SIDE EFFECTS
------------
The latest CLEAN model will be added to the established model
component list and model visibilities. If this is undesirable then use
the 'clrmod' command to clear the latest CLEAN model before inverting.

RELATED COMMANDS
----------------
mapsize  - Specify the dimensions of subsequent maps.
uvweight - Selects combinations of natural,uniform, uncertainty, and
           radial weighting.
uvtaper  - Apply a gaussian taper to the weights.
uvrange  - Constrain the range of UV radii within which to select
           visibilities for gridding.
uvzero   - Set a zero-UV-spacing flux.
```

keep

```
Establish the latest CLEAN model and compute its UV representation.

  keep

EXAMPLE
-------

0>keep
Computing UV representation of latest clean model (91 components)
The established model now contains 182 components and 8.18052 Jy
0>

All but the first line are responses from the 'keep' command.

CONTEXT
-------
During mapping, two separate CLEAN models are kept. These are the
"established model" and the "latest clean model". The former is
subtracted from the visibilities during invert and is kept both as a
model component list AND as model visibilities in the UV plane. The
latter - the latest clean model - is the model that has been
accumulated by CLEANing since the last time that 'keep' was run. Also
if a model is read from an external file using the 'rmodel' command
then it replaces the latest clean model and deletes the established
model. The latest clean model is added in to the established model
and converted to its UV representation every time that the 'keep'
command is called. There is rarely a need to do this explicitly, since
commands that require the UV representation of the complete model,
call 'keep' for you. Such commands include 'invert', 'selfcal' and
'vplot'. However, if you just keep cleaning the residual map without
calling any of these other commands then to remove aliased artifacts
it may be desireable to call the 'keep' command explicity once in a
while.

A separate UV plane representation of the established model is kept
for each IF, in the uvmodel.scr scratch file, and automatically paged
in and out by difmap as required.

RELATED COMMANDS
----------------
clrmod  - Used to clear one or more of the established, tentative and
          continuum models.
```

loglevs

```
Set logarithmic contour levels for mapplot.

  loglevs min, max, base


EXAMPLE
-------

0>loglevs 0.5
The new contour levels are:
 -0.5 0.5 1 2 4 8 16 32 64
0>

The second and third lines are output lines from loglevs and show the
resulting levels assigned to the levs variable.

PARAMETERS
----------
min  -  The lowest (positive) level to include. The levels list starts
        with  -min,min,... ie. The first positive level is also used as
        the only negative value.

max  -  (Optional: Default=100)
        This is the highest (positive) level to include in the levels
        listing. Thus:  loglevs 0.5,2  produces  -0.5,0.5,1,2 .

base -  (Optional: Default=2)
        The scale factor between subsequent levels in the listing.
        Thus:  loglevs 0.5,2,1.5  produces  -0.5 0.5 0.75 1.125 1.6875 .

CONTEXT
-------
The full dynamic range of a contour plot is often most cleanly
represented by an exponentially increasing set of contour levels
(conventionally called logarithmic levels).

The contour levels used by subsequent calls to the mapplot command
are defined in a user-variable called  levs. One way to set these
levels is to directly assign them:

For example:

0> cmul=0
0> levs=-1,1,2,4,8,16,32,64

Defines a set of percentage contour levels starting at -1% and
increasing exponentially up to 64%.
```

```
It is tedious to have to type out the levels explicitly in this
way. The loglevs command provides a more convenient means to
assigning "logarithmic" levels to the levs variable. Thus the
above example could be achieved by typing:

0> cmul=0
0> loglevs -1

RELATED COMMANDS
----------------
mapplot  -  Display map and beam images.
xyrange  -  Set the boundaries of the sub-image to be displayed in mapplot.
loglevs  -  Set logarithmic levels.
mapcolor -  Select mapplot colormap type and transfer function.
mapfunc  -  Change the transfer function used in mapplot.
beamloc  -  Change when and where mapplot plots the clean beam ellipse.
```

mapcolor

```
Select the colormap type, brightness and contrast to use in mapplot.

  mapcolor type, contrast, brightness

EXAMPLES
--------

1. To disable psuedo-color plotting.

   0>mapcolor none
   Mapplot colormap: none, contrast: 1 brightness: 0.5.
   0>

2. To select a grey-scale color map.

   0>mapcol grey
   Mapplot colormap: grey, contrast: 1 brightness: 0.5.
   0>

3. To select the current default color colormap:

   0>mapcolor color
   Mapplot colormap: rainbow, contrast: 1 brightness: 0.5.
   0>

4. To change the default colormap to the AIPS TVFIDDLE colormap
   and select it for the next mapplot:

   0>mapcolor aips
   Mapplot colormap: aips, contrast: 1 brightness: 0.5.
   0>

PARAMETERS
----------

     type  -  The type of colormap to use, selected from:
                 none   -   Turn off psuedo-color plotting.
                 grey   -   Use a grey-scale ramp [initial default].
                 color  -   Use the default RGB colormap.
                 aips   -   The AIPS TVFIDDLE colormap.
                 heat   -   Flame colored colormap.
                 ramp   -   This is a three ramp colormap, based on
                            one in Iraf's ximtool.
                 red    -   Red ramp.
                 green  -   Green ramp.
                 blue   -   Blue ramp.

brightness -  The brightness of the color bar between 0 and 1.
```

```
                With the gray-scale colormap, the image will be
                completely black for brightness <= 0, and completely
                white at brightness >= 1.

                The initial default is 0.5, which places the center
                of the colormap at the center of the color bar.

contrast    -   The contrast of the colormap, expressed as the reciprocal
                of the width of the colormap on the displayed color bar.
                The initial default of 1.0 spreads the colormap over the
                length of the color bar. Higher contrasts compress the
                colormap, while lower contrasts expand it.

CONTEXT
-------
Mapplot can display maps using contours, and/or grey-scale or
psuedo-color. The colormap command provides a means of selecting
these options prior to running mapplot. There are three classes
of colormap that you can choose:

   none - This turns off grey-scale and color plotting entirely.

   grey - This selects the default grey-scale colormap.

  color - All colormaps except those named above, are of class
          'color'. Specifying 'color' to the colormap command
          selects the last colormap of class 'color' that was
          previously selected. Thus after selecting 'aips' once,
          either interactively in 'mapplot', or via the mapcolor
          command, and then subsequent requests for 'color'
          install the 'aips' colormap. Other 'color' color-maps
          are listed above under the explanation of the 'type'
          argument.

You also have the option of specifying how the colormap will be
mapped onto the mapplot image intensity. By default, the contrast
is set to 1 and the brightness to 0.5. This fits the colormap exactly
within the color bar plotted under the mapplot image. The center of
the colormap can be moved up or down the color bar by changing the
colormap brightness. This is best done interactively in mapplot,
but can also be set on the command line with the mapcolor command.
The width of the colormap compared to that of the color bar can also
be changed by altering the contrast. High contrast equates to a
colormap that occupies only a small fraction of the color bar. Low
contrast equates to a colormap extent that exceeds the width of the
color bar, such that only a small range of its colors are visible.
Negative contrasts act the same as positive contrasts except that the
colormap is reversed. Again, the contrast is best set interactively
in mapplot, but can be preset with the 'mapcolor' command.
```

```
Note that to completely flip the sense of a color map you should
first run the mapcolor command without arguments, to see what the
current brightness and contrast are. Then run the mapcolor command and
substitute -contrast for the original contrast, and 1-brightness for
the original brightness.

To see what the current colormap settings are, invoke the colormap
command with no arguments.

Note that changes to the colormap selection, brightness and
contrast within mapplot remain in place after you exit mapplot.
It is thus possible to set these parameters interactively in mapplot
for subsequent mapplot plots. In particular, this is invaluable for
making hard copies in color after setting the desired colors on
an interactive device.

Also see 'help mapfunc' for details on how to specify the transfer
function and data range to plot.

Limitations
-----------
When using this command note that:

1. Some devices are not capable of displaying color. In such
   cases RGB colormap types will be translated into grey-levels. This
   is device dependant and the results may not be what you expect.

2. Some devices can't even display different levels of grey.
   On such devices a random-stipple pattern is used to simulate
   different grey-levels.

3. If you are using an old version of PGPLOT that does not have
   the PGIMAG call, then only grey-scale colormaps are generally
   available on hard-copy devices.

RELATED COMMANDS
----------------
mapplot  -  Display map and beam images.
xyrange  -  Set the boundaries of the sub-image to be displayed in mapplot.
loglevs  -  Set logarithmic contour levels for use in 'mapplot'.
mapfunc  -  Change the transfer function used in mapplot.
mapplot  -  Display map and beam images.
beamloc  -  Change when and where mapplot plots the clean beam ellipse.
```

mapfunc

```
Change the transfer function and data range displayed in mapplot.

  mapfunc function, vmin, vmax

EXAMPLES
--------

To select a linear transfer function:

 0>mapfunc linear
 Mapplot transfer-function = linear, Data range = data min -> data max.
 0>

To select a logarithmic transfer function, and limit the range of
fluxes displayed:

 0>mapfunc log, peak(flux,min), peak(flux,max)/2
 Mapplot transfer-function = log, Data range = -0.103472 -> 0.162955 Jy.
 0>

To select the whole available data range:

 0>mapfunc linear,0,0
 Mapplot transfer-function = linear, Data range = data min -> data max.
 0>

PARAMETERS
----------

 function  -  The transfer function to use, selected from:
               linear -   Linear transfer function.
               log    -   Logarithmic transfer function.
               sqrt   -   Square-root transfer function.

 vmin      -  The minimum map intensity to be plotted (Jy).

 vmax      -  The maximum map intensity to be plotted (Jy).
              To select the whole data range, set vmin and vmax
              both to zero.

CONTEXT
-------
Mapplot displays images using contours and/or grey-scale/psuedo-color
plots. When grey-scale or psuedo-color are selected (see help
mapcolor), mapplot defaults to mapping the whole range of data in the
map or beam, linearly onto the current colormap. In high dynamic range
images with bright features this has the tendency of making low
brightness features difficult to see. In such cases it is often
```

```
advantageous to take the log or square root of the image values,
and/or reduce the maximum intensity plotted. The 'mapfunc' command
allows one to do this.

Note that mapplot also  allows one to interactively change the
transfer function (but not the data range).

Also note that older versions of PGPLOT did not allow one to change
the transfer function, and if you are using such a version, all
transfer functions will appear linear.

RELATED COMMANDS
----------------
mapplot  -  Display map and beam images.
mapcolor -  Change the colormap, brightness and contrast used in mapplot.
xyrange  -  Set the boundaries of the sub-image to be displayed in mapplot.
loglevs  -  Set logarithmic contour levels for use in 'mapplot'.
beamloc  -  Change when and where mapplot plots the clean beam ellipse.
```

maplot

```
Alternative name for the mapplot command - see help mapplot.

  maplot beam_map_cln, domodel
```

mapplot

```
Display the dirty beam, residual or restored map and modify CLEAN windows.

  mapplot beam_map_cln, domodel

EXAMPLE 1
---------

0>mapplot beam
Graphics device/type (? to see list, default /NULL): /xw
Move the cursor into the plot window and press 'H' for help
0>

In the above example, no PGPLOT display device had previously been
opened so the second line requests the PGPLOT display device.
Once this has been entered, future uses of mapplot will not require
the device name to be entered. The plot device can be changed with
the "device" command.

0> mapplot map,true

This plots the residual map overlayed with symbols for each model
component.

PARAMETERS
----------
beam_map_cln -  (Default = map)
                The only valid arguments are 'map', 'beam' and 'cln'.
                 mapplot map   -  displays the map,
                 mapplot beam  -  displays the dirty beam,
                 mapplot cln   -  displays the restored map (after
                                  restoring when necessary).

domodel      -  (Default = false)
                If true then any model components that have been
                accumulated will be plotted symbolically.
                Delta components are denoted by '+' symbols, and others
                by their elliptical outline. Positive components
                are drawn in green and negative components in red.
                Variable components are plotted in yellow (orange if
                negative).

RUNNING PARAMETERS
------------------
There are a number of auxiliary parameters that don't appear in the
argument list. Some of these parameters exist as variables, while
others are commands. All are listed below.

False color plotting
```

```
====================

Commands:

 mapcolor  -  The 'mapcolor' command allows one to pre-select the
              color table, brightness and contrast under which mapplot
              maps will be plotted.
              See 'help mapcolor' for further details.

 mapfunc   -  The 'mapfunc' command allows one to select the transfer
              function with which the maps in mapplot will be plotted
              and to specify the range of intensities to be displayed.
              See 'help mapfunc' for further details.

contour plotting
================

Variables:

    docont -  If docont==true then future use of 'mapplot' to plot the
              restored map will include a contour representation of
              the clean map. This parameter is ignored when plotting
              the beam and residual maps if false-color has also been
              selected. Docont is initially defined as docont=true.

    levs   -  A 1-D array of contour levels. If this has not been set
              then the default percentage levels of
              -1,1,2,4,8,16,32,64 are used for the map and
              -64,-16,-4,4,16,32,64 for the beam. If valid contour
              levels are given, they are treated as percentage levels
              if 'cmul' is <= 0, or as absolute levels pre-scaled by
              'cmul' otherwise.
Commands:

 loglevs   -  This command provides a short cut to setting the 'levs'
              variable described above. It sets the contour levels to
              a logarithmic ramp. See 'help loglevs' for further details.

Note that only levels that appear in the displayed area are presented
in the list of levels that is written beneath the plot.

Restricting the plotted display range
=====================================
By default, the whole available map or beam area is displayed when
you invoke mapplot. To change this behavior use the xyrange command
(see help xyrange) to select the required sub-image for subsequent
calls to mapplot. Alternatively, the displayed area can be changed
interactively with the cursor and optionally saved for later
calls to mapplot - see below.
```

```
USE OF THE CURSOR
-----------------
If your display device has the capability to display a graphics cursor,
then this will be displayed and you will be able to (among other
things) add or remove CLEAN windows. The options are selected by
pressing any of the keyboard or mouse keys given below (the cursor
must be within the display window). In particular, to get a list of
key bindings while running mapplot, hit the 'H' key on your keyboard
and the list will be displayed in your terminal window.

NB. If you have a mouse, the following keys are bound to the mouse
    buttons.
      A - Left mouse button.
      D - Middle mouse button.
      X - Right mouse button.

Mapplot cursor key Bindings
===========================

Key 'A' (left-button)   Set a window vertex. (ie move the cursor to
                        where the start vertex is required and press
                        'A', then move the cursor to the desired
                        position of the opposite corner and again press
                        'A' and the new window will be drawn.
Key 'D' (middle-button) Delete the CLEAN window which has one of its
                        corners closer to the cursor than any other
                        window. This key may also be used to cancel a
                        partially complete window selection.
Key 'C'                 This switches from gray-scale to a pseudo-color
                        plot.
Key 'G'                 Re-plots gray-scale after 'C' has been pressed.
Key 'S'                 Display statistics of the region of the map
                        inside a CLEAN window. This includes the total
                        flux only if the displayed map is a restored
                        map. The window used is the one that has one of
                        its corners closer to the cursor than any
                        other window.
Key 'V'                 Report value and coordinates of the pixel that
                        lies immediately under the cursor.
Key 'Z'                 Select a sub-image to be displayed by pressing
                        the 'A' key at two opposite corners of the
                        required area.
                        To cancel sub-image selection, press 'D' at any
                        point during the selection. To zoom out back to
                        the full display area, press 'Z' a second time.
Key 'K'                 Pressing this key will tell mapplot to remember
                        the current sub-image boundaries on the next
                        call to mapplot.
Key 'f' (lower case)    Pressing this key over a particular position in
                        the plot changes the brightness and contrast of
```

```
                        the displayed colormap. The X-axis position
                        of the cursor controls the brightness, increasing
                        from left to right. The Y-axis position controls
                        the contrast, with 0 contrast in the middle of the
                        plot, positive contrasts below this and negative
                        contrasts above.
Key 'F'                 This resets the colormap brightness and contrast
                        to the defaults: brightness=1.0, contrast=0.5.
Key 'c' (lower case)    This changes the colormap from grey-scale to the
                        default color colormap.
Key 'C'                 This allows you to select a colormap by name.
                        At the prompt, type in the name of the required
                        colormap, or enter nothing to leave things as
                        they are.
Key 'T'                 Re-display the plot with a specified transfer
                        function (log,linear,sqrt). At the prompt,
                        enter the name of the transfer function required.
Key 'L'                 Re-display the current plot.
Key 'm' (lower case)    This toggles whether to overlay a symbolic
                        representation of the model on the map.
Key 'M' (upper case)    This toggles whether to overlay a symbolic
                        representation of just the variable components
                        of the model on the map.
Key 'N'                 Initiate creation of a new model component -
                        see later.
Key 'R'                 Remove the component that has the closest center
                        to the cursor. This deletes the component from
                        the established or tentative model of the
                        observation. Note that if you plan to delete
                        many components a faster way is to use the
                        difmap 'winmod' command.
Key 'H'                 Display list of key bindings.

Key 'X' (right-button)  Exit from 'mapplot'.

DISPLAYING RESTORED MAPS
------------------------
There are two ways of having the map restored and plotted.
You can either call the 'restore' command explicitly then type
'mapplot cln', or simply type 'mapplot cln'. For example:

0>restore 1.2,2.5,-32
0>mapplot cln

or

0> mapplot cln

In the first case a non-default restoring beam size was required
so restore was invoked explicitly. In the second case restore is
```

called by mapplot, with no arguments.

Note that if you typed:

```
0>restore 1.2,2.5,-32
0>mapplot
```

then since mapplot defaults to plotting the residual map when given no arguments, it will re-invert the data and display the residual map - take care!

SIDE EFFECTS

Note that changes to the colormap selection, brightness and contrast within mapplot remain in place after you exit mapplot. It is thus possible to set these parameters interactively in mapplot for subsequent mapplot plots. In particular, this is invaluable for making hard copies in color after setting the desired colors on an interactive device.

When displaying a residual map or dirty beam the UV data will be re-inverted if recent changes to the grid weighting or modifications to the data itself, eg. editing, make the current residual map out of date.

When plotting the restored map (using the cln option) the map will be restored if an up-to-date restored map has not already been created with the 'restore' command. In this case 'restore' will be called with no arguments.

If new components are interactively added, or deleted then the map will be marked as out of date and will be re-inverted the next time that it is required.

MODEL COMPONENT CREATION AND DELETION

Maplot can be used to interactively add and/or remove variable model components pertinent to subsequent model fitting. Other forms of variable model component editing should be performed with the difmap 'edmod' command. The changes to the map itself are NOT displayed as model components are added and removed. This would take too long. Only changes to the symbolic outlines of components are displayed.

The syntax used to create a component is as follows:

Press 'N' to initiate description of a new component.

Press 'A' (left-mouse-button) between 0 and 3 times, to describe
the position and dimensions of the new component.

Press 'N' to install the component, or press 'D' (middle-mouse-button)
to cancel the component.

Each press of the 'A' key over a point in the map describes one more variable feature of the component, starting from a delta component at the center of the map. The optional steps (0 selections to 3 selections) are as follows:

0. If 'N' is pressed without having described any parameters then a delta component will be placed at the center of the map.

1. The first click of the 'A' key over a selected point in the map defines the position of the center of the new component. A dot is plotted to indicate its position.

   Pressing 'N' at this point installs a delta-component at this position.

2. A second click of the 'A' key over another selected position in the map defines the axis of a circular gaussian, as the line joining the selected component center to the newly selected position. This line is drawn so that one can judge its veracity.

   Pressing 'N' at this point installs a circular gaussian with the axial ratio and axial position angle as fixed parameters.

3. A third click of the 'A' key describes the second axis of an elliptical gaussian component via its distance from the selected component center. The position angle of the first axis selected (in step 2 above) defines the major axis position angle. A line is drawn at right angles to the first axis so that one can check its veracity.

   Pressing 'N' at this point installs an elliptical gaussian with all parameters variable. Pressing 'D' cancels the component.

Once the component is installed, its symbol representation is displayed.

If the component turns out to be poorly described, you can then delete it with the 'R' (remove component) key.

Note that the flux given to the component is simply the flux of the pixel under its center. This is not a very good choice, but it is hard to see what would be a good choice, especially given that the map is not re-inverted and re-displayed in maplot each time a new component is added or removed. If you have a better idea of what the component flux should be, use the difmap 'edmod' command to change it. Alternatively let the difmap 'modelfit' command find it for you.

EXTENDED EXAMPLE

```
----------------
To plot a restored map with non-default percentage contours and a reduced
grey-scale saturation flux:

mapfunc linear, -1, 0.5
levs=-0.1,0.1,0.25,0.5,1,2,4,8,16,32,64
cmul=0
mapplot cln

In the above case, the levs= assignment could be avoided by using
the loglevs command.

loglevs 0.1

See help loglevs for more details.

RELATED COMMANDS
----------------
xyrange  - Set the boundaries of the sub-image to be displayed in mapplot.
loglevs  - Set logarithmic levels.
mapcolor - Select mapplot colormap type and transfer function.
mapfunc  - Change the transfer function used in mapplot.
beamloc  - Change when and where to plot the clean beam ellipse.
```

mapsize

```
Request a new map grid of given width and cell size

  mapsize nx, dx, ny, dy

EXAMPLES
--------

1. To request a square map with square pixels:

   0>mapsize 256,0.5
   Map grid = 256x256 pixels with 0.5x0.5 milli-arcsec cellsize.
   0>

2. To request a rectangular grid with rectangular pixels.

   0>maps 256,0.5,128,1.0
   New map grid = 256x128 pixels with 0.5x1.0 milli-arcsec cellsize.
   0>

3. To see what the current map size is, omit all arguments:

   0>maps
   Map grid = 256x128 pixels with 0.500x1.00 milli-arcsec cellsize.
   0>

The second line of each example shows the response from the 'mapsize'
command, confirming what was typed.

PARAMETERS
----------
nx   -  The number of pixels along the X-axis map and beam grids.
        This number must be positive and be an integer power of 2,
        such as 256 or 512 or 1024.

dx   -  This is the width of each pixel along the X-axis. Unless
        changed with the mapunits command, the units are milli-arcsec.

ny   -  Optional: If not provided, ny is given the value of nx.
        The number of pixels along the Y-axis map and beam grids.
        This number must be positive and be an integer power of 2,
        such as 256 or 512 or 1024.

dy   -  Optional: If not provided, dy is given the value of dx.
        This is the width of each pixel along the Y-axis. Unless
        changed with the mapunits command, the units are milli-arcsec.

SIDE EFFECTS
------------
```

Any existing map will be destroyed, and the new map will be
initialized to contain 0.0 in each element.

CONTEXT

This command specifies the size of the grid to use to sample the map
and beam in the image plane. All commands that operate on maps, such
as 'clean', 'restore', 'mapplot' and 'invert', require that such a
grid be created before they are invoked. 'mapsize' may be called
at any time thereafter to change the size of the map or beam arrays.

The maxmimum size of the map and beam grids is limited only by the
amount of memory available on your computer. Note that the amount of
memory required by the two arrays is 2.(nx.ny).sizeof(float) bytes.
If sizeof(float) is 4 bytes, then the following numbers apply for
square grids:

nx=ny	Memory
128	131 Kb
256	524 Kb
512	2.0 Mb
1024	8.4 Mb
2048	34.0 Mb

Clearly, large grids require large amounts of memory, take a much
longer time to process and may cause your computer to page heavily.
For this reason it is beneficial to use the smallest grid that can
accomodate the region of interest. In particular, if there are many
sources to be mapped, scattered over a wide area, it may be faster to
partially map each source separately, using the 'shift' command to
temporarily shift each source into the center of a smaller map area.

CHOOSING THE CELL SIZE

The appropriate choice of cellsize along the X and Y axes of a
map grid depends on the sampling of the UV plane by visibilities. To
sample the finer detail in the image-plane implied by larger U or V
coordinates, requires smaller cell sizes in the map. In particular, to
avoid undersampling the image plane, the highest spatial frequencies
sampled by the UV data must have a period of at least two pixels. This
contraint applies separately to spatial frequencies along the X and Y
axes of the map.

In theory, if the maximum absolute U and V coordinates sampled are
umax and vmax (wavelengths), then the corresponding maxmimum cellsizes
along the corresponding X and Y axes of the map and beam, are given by:

```
  dx = 1/(4.umax + 2)  radians  =>  2.063e8/(4.umax + 2)  milli-arcsec
  dy = 1/(4.vmax + 2)  radians  =>  2.063e8/(4.vmax + 2)  milli-arcsec
```

where the "+ 2" component is due to the 2 pixel fuzz introduced by the convolution function that is used to interpolate visibilities onto a regular grid.

This constraint is enforced by the difmap 'invert' command, whose job it is to create a dirty map and beam from the visibility data. Visibilities that represent higher spatial frequencies than can be Nyquist sampled by the chosen pixel size are excluded from the maps that it creates. When it does this, the 'invert' command tells you what percentage of the visibilities had to be excluded and displays the above limiting values of dx and dy so that you can, if you want, change the map grid to avoid omitting any data from subsequent maps. Note that it is not necessarily an error to choose a cell size that is too big to sample all of the visibilities. Sometimes this is the only practicle way to create a map that is large enough to view one's field of interest.

Also note that because the standard CLEAN algorithm only cleans the inner nx/2 by ny/2 pixels of the map, the maximum map area cleanable by 'clean' and displayed by 'mapplot' is actually the area:

```
  X range  =  -nx/(4.umax+2)/2 -> +nx/(4.umax+2)/2
  Y range  =  -ny/(4.umax+2)/2 -> +ny/(4.umax+2)/2
```

RELATED COMMANDS

```
invert  - Invert the UV visibility residuals to form a residual map
          and dirty beam.
restore - Combine model components and a residual map to produce a
          clean map.
mapplot - Display the residual or clean map, or dirty beam.
```

mapunits

```
Change the units used to specify and label map and UV plane distances.

  mapunits unit

EXAMPLES
--------

0>
0>mapunit mas
Distances in the map plane now have units: milli-arcsec.
Distances in the UV plane now have units: mega-wavelengths.
0>

0>mapunit arcsec
Distances in the map plane now have units: arcsec.
Distances in the UV plane now have units: kilo-wavelengths.
0>

0>mapunit
Distances in the map plane now have units: arcsec.
Distances in the UV plane now have units: kilo-wavelengths.
0>

ARGUMENTS
---------
unit     -   Optional.
             One of the following distance units:
               mas    -  Milli-arcseconds and mega-wavelengths.
               arcsec -  Arcseconds and kilo-wavelengths.
               arcmin -  Arcminutes and kilo-wavelengths.
             If no name is provided, then the current settings are
             reported without modification, as in the third example
             above.

CONTEXT
-------
VLBI antennas are generally separated by a few million wavelengths and
are sensitive to source structure at the milli-arcsecond scale. The
natural units to express these characteristics are thus
milli-arcseconds in the map plane, and mega-lambda in the UV plane.

Other more compact arrays such as the VLA, generally have baseline
lengths that are more naturally expressed in kilo-wavelengths, and are
sensitive to source structure at the arcsecond scale.

Since there is no one set of units that satisfies all observations,
difmap gives you the choice of a few units. The chosen units refer
both to the units of the arguments to difmap commands, and to how
```

distances are displayed and labelled by difmap.

Unless the 'mapunits' command is invoked to change the units, difmap sets the map-plane distance units to milli-arcseconds and the baseline length units to mega-wavelengths. This reflects difmap's VLBI heritage.

mapvalue

```
Return the value of the map pixel nearest to a given coordinate.

  mapvalue x, y

EXAMPLE
-------

1. The following use of mapval() displays the flux in the map at
   a position 3.5 arcsec to the east and 0.7 arcsec to the north
   of the center of the map.

    0>mapunits arcsec
    Distances in the map plane now have units: arcsec.
    Distances in the UV plane now have units: kilo-wavelengths.
    0>print mapval(3.5,0.7)
    0.293557
    0>

2. The flux at the center of the map can be displayed with:

    0>print mapval(0,0)
    3.44326
    0>

PARAMETERS
----------

x     - The X offset with respect to the center of the map, as
        displayed by maplot.

y     - The Y offset with respect to the center of the map, as
        displayed by maplot.

SIDE-EFFECTS
------------
If the map is out of date with the UV data then it will be re-inverted
before returning a value.

RELATED FUNCTIONS
-----------------
peak    - Return details of the min,max or absolute max flux in a map.
imstat - Return image plane map statistics.
```

modelfit

```
Fit image-plane model components to visibilities in the UV plane.

  modelfit niter

EXAMPLE
-------

 0>modelfit 4
 Partitioning the model into established and variable parts.
 The fixed established model contains 0 components (0 Jy).
 The variable part of the model contains 2 components (0.97 Jy).
 There are 10 variables and 4510 usable visibilities.
 This gives 2 x 4510 - 10 = 9010 degrees of freedom.
 Reduced Chi-squared = Chi-squared / 9010.

 Iteration 00: Reduced Chi-squared=46.315838
 ! Flux (Jy) Radius (mas)  Theta (deg)  Major (mas)  Axial ratio   Phi (deg) T
   0.950000v     0.00000      0.00000      1.00000v     1.00000v    0.00000v 1
  0.0200000v     1.00000v    -130.000v     1.00000v     1.00000v    0.00000v 1

 Iteration 01: Reduced Chi-squared=4.3881679
 ! Flux (Jy) Radius (mas)  Theta (deg)  Major (mas)  Axial ratio   Phi (deg) T
   0.416386v     0.00000      0.00000     0.524179v    0.437841v   -6.49258v 1
  0.0826878v     1.00780v    -137.060v     3.31603v    0.732082v   -56.6298v 1

 Iteration 02: Reduced Chi-squared=0.89815858
 ! Flux (Jy) Radius (mas)  Theta (deg)  Major (mas)  Axial ratio   Phi (deg) T
   0.493566v     0.00000      0.00000     0.371532v    0.167305v   -7.53078v 1
  0.0209711v     1.20514v    -165.679v     3.93011v    0.331629v   -49.3905v 1

 Iteration 03: Reduced Chi-squared=1.0050499 (Increased)
 Iteration 04: Reduced Chi-squared=1.0088361 (Increased)
 0>

ARGUMENTS
---------

niter   -   The number of iterations to try, or zero to just see the
            current fit. 10 and 20 are good numbers to try, before the
            first selfcal.

CONTEXT
-------
Model fitting directly to the visibilities of interferometric data has
two common uses.

1. It is employed to find good starting models for the initial phase
   self-calibration of phase-unstable data, especially when a point
```

source starting model has proved insufficient.

2. It is commonly used to parameterise the general characteristics of sources with as few variables as possible.

The difmap modelfit program fits aggregates of various forms of model components, fitting directly to the real and imaginary parts of the observed visibilities using the powerful Levenberg-Marquardt non-linear least squares minimization technique. This makes it substantially faster and a lesser consumer of memory than the Caltech VLBI package modelfit program, that fitted to an ad hoc combination of closure-phase and amplitude.

The disadvantage of the newer algorithm is that it assumes that the phases are well calibrated. The older algorithm was insensitive to this through its use of closure phases. As a result, using modelfit in difmap may require a number of interleaved self-calibration steps to converge on the model that agrees well with the closure phases.

SPECIFYING MODELS FOR MODELFIT

There are three ways to specify model components to modelfit.

1. In model files, components with variable parameters are denoted by a 'v' character post-fixing each of the variable parameters.

   Thus in the following model the first component is an elliptical gaussian component with all parameters variable except its position, while the second component has all parameters variable.

```
 ! Flux (Jy) Radius (mas)  Theta (deg)  Major (mas)  Axial ratio   Phi (deg) T
   0.140490v     0.00000      0.00000     0.704297v    0.147144v   -48.4654v 1
   0.118984v     1.01917v     137.776v     1.10527v    0.544262v   -57.5779v 1
```

   The meaning of each of the above parameters (as originally defined for the Caltech VLBI package), is as follows:

   Flux - The integrated flux in the component (Jy).
   Radius - The radial distance of the component center from the center of the map (milli-arcsec).
   Theta - The position angle of the center of the component (degrees North -> East) wrt an imaginary line drawn vertically through the map center.

   The following components may be omitted for delta components.

   Major - The FWHM major axis of the elliptically stretched component (milli-arcsec).
   Ratio - The ratio of the minor axis to the major axis (0 -> 1).
   Phi - The Position angle of the major axis (degrees North -> East).

```
   T       -  The type of component. Recognised types are:

                0 - Delta function.
                1 - Gaussian.
                2 - Uniformly bright disk.
                3 - Optically thin sphere.
                4 - Ring.
                5 - Un-supported component type - kept for compatibility.
                6 - Sunyeav-Zel'dovich.

   Internally the positions of components are recorded by their X and Y
   axis positions wrt the map center and fitting is wrt these parameters.
   For this reason if either Radius or Theta is made variable, both will
   be taken as variable. It is not possible to fix one or the other
   individually. Similarly, except for the special case of a circular
   component where only Major is marked as variable and the axial ratio
   is exactly 1.0, it is not possible to individually mark Major,Ratio
   and Phi to be fixed. Marking one as variable sets them all as variable.

   More obviously, the model component type T can not be marked to be
   variable.

2. While model components can be specified via a model file in the
   above format, it is usually more convenient to incrementally add
   and remove components interactively via the difmap 'mapplot'
   command. See help mapplot for further details.

3. The final method is really directed towards changing the trial
   parameters of an existing variable model, although new components
   may also be created. This method uses the difmap 'edmodel' command,
   which invokes an editor on an internally generated model scratch
   file, initialized with the existing variable model components,
   appropriately shifted if the 'shift' command has previously been
   used. See help edmodel for further details.

RELATED COMMANDS
----------------
edmodel - Edit the current models with an external editor.
rmodel  - Read a new model for modelfit.
mapplot - Maplot allows interactive addition and removal of
          components.
addcmp  - Add a model component by hand to the tentative model.
```

nbase

```
Return the number of baselines in a given sub-array.

  nbase subarray

EXAMPLE
-------

Example 1  -  Write a message saying how many baselines are in
              sub-array 1.

0> print "There are", nbase, "baselines in sub-array 1"
There are 10 baselines in sub-array 1.

Example 2  -  List the names of all 'nbase' baselines in sub-array 2.

0> do i=1,nbase(2)
1>   print basename(i,2)
1> end do
WSRT-BOLOGNA
WSRT-HSTK
BOLOGNA-HSTK
WSRT-VLBA_KP
BOLOGNA-VLBA_KP
HSTK-VLBA_KP
WSRT-VLBA_LA
BOLOGNA-VLBA_LA
HSTK-VLBA_LA
VLBA_KP-VLBA_LA
0>

PARAMETERS
----------
subarray  -  Optional: Defaults to 1.
             This is the number of the antenna sub-array to return the
             baseline count from. The 'header' command may be used to
             examine what sub-arrays are available.

RELATED FUNCTIONS
-----------------
basename  -  Return the name of the n'th baseline of a given sub-array.
```

nchan

```
Return the count of the number of spectral-line channels per IF.

  nchan

EXAMPLE
-------

0>print "There are", nchan, "spectral-line channels."
There are 96 spectral-line channels.
0>

CONTEXT
-------
'nchan()' is a function that returns the integer count of the number
of spectral-line channels per IF of the current observation.

RELATED FUNCTIONS AND COMMANDS
------------------------------
nif    -  Return the number of IFs in the current observation.
nsub   -  Return the number of sub-arrays in the current observation.
nbase  -  Return the number of baselines in a given sub-array.
ntel   -  Return the number of telescopes in a given sub-array.
header -  Displays the characteristics of the current observation.
```

nif

Return the number of IFs in the current observation.

```
  nif
```

EXAMPLE

```
0>print "There are", nif, "IFs in the current observation."
There are 2 IFs in the current observation.
0>
```

CONTEXT
----

nif() is a function that returns the integer count of the number of IFs in the current observation.

RELATED FUNCTIONS AND COMMANDS

```
nchan  -  Return the number of spectral-line channels per IF.
nsub   -  Return the number of sub-arrays in the current observation.
nbase  -  Return the number of baselines in a given sub-array.
ntel   -  Return the number of telescopes in a given sub-array.
header -  Displays the characteristics of the current observation.
```

nsub

Return the number of sub-arrays in the current observation.

```
  nsub
```

EXAMPLE

```
0>print "There are", nsub, "sub-arrays in the current observation."
There are 4 sub-arrays in the current observation.
0>
```

CONTEXT
----

nsub() is a function that returns the integer count of the number of telescope sub-arrays per IF of the current observation.

RELATED FUNCTIONS AND COMMANDS

```
nif    -  Return the number of IFs in the current observation.
nchan  -  Return the number of spectral-line channels per IF.
nbase  -  Return the number of baselines in a given sub-array.
ntel   -  Return the number of telescopes in a given sub-array.
header -  Displays the characteristics of the current observation.
```

ntel

```
Return the number of telescopes in a given sub-array.

  ntel subarray

EXAMPLE
-------

Example 1  -  Write a message saying how many telescopes are in the first
              sub-array.

0> print "There are", ntel, "telescopes in sub-array 1"
There are 13 telescopes in sub-array 1

Example 2  -  List the names of all 'ntel' telescopes in sub-array 2.

0> do i=1,ntel(2)
1>   print telname(i,2)
1> end do
BONN
WSRT
JBNK1
BOLOGNA
VLBA_KP
VLBA_PT
VLBA_LA
VLA27
OVRO
0>

PARAMETERS
----------
subarray  -  Optional: Defaults to 1.
             This is the number of the antenna sub-array to return the
             telescope count from. The 'header' command may be used to
             examine what sub-arrays are available.

RELATED FUNCTIONS
-----------------
telname  -  Return the name of the n'th telescope of a given sub-array.
```

observe

```
Read UV data from a random-groups UV FITS file.

  observe file_name, bin_width, do_scatter

EXAMPLE
-------

  0>observe /scr/mcs/fits/gbt_spec.uvf
  Reading UV FITS file: /scr/mcs/fits/gbt_spec.uvf
  AN table 1: 7 integrations on 45 of 45 possible baselines.
  Apparent sampling: 1 visibilities/baseline/integration-bin.
  Found source: 1641+399

  There are 2 IFs, and a total of 128 channels:

   IF  Channel    Frequency  Freq offset  Number of   Overall IF
        origin    at origin  per channel   channels    bandwidth
   ------------------------------------------------------------ (Hz)
   01        1  1.53575e+10       125000         64        8e+06
   02       65  1.53655e+10       125000         64        8e+06

  Polarization(s): RR LL RL LR

  Read 353 lines of history.

  Reading 161280 visibilities.
  0>

All lines following the 'observe' command line are informational output
messages from the observe command.

PARAMETERS
----------
file_name  -   The name of the UV FITS file to be read.

bin_width  -   Default=0.0 (seconds)
               This argument is used to specify how visibilities are
               to be collected into integrations. This is discussed
               further in the CONTEXT section below. There are two
               alternatives:

               1. If binwid<1.0 seconds then 'observe' will assign an
                  integration to every time-stamp in the file. This is
                  ok if visibilities on different baselines within the
                  same integration have the same time-stamps, but
                  disasterous otherwise.

               2. If binwid>=1.0 seconds then 'observe' will bin
```

```
                visibilities onto a regular integration grid of
                spacing 'binwid' seconds anchored at 0 UTC on the
                first day of the observation. Where multiple
                visibilities fall on the same baseline of a given
                integration, they will be vector averaged using a
                weighted mean using the same algorithm as uvaver.

do_scatter -   Default=false
               If do_scatter=true the weights from the FITS file
               will be supplanted by weights estimated from the
               scatter of the data within each integration bin. There
               must be at least two visibilities per baseline within each
               integration bin to do this. Where this is not the case
               the output visibility will be flagged, and be assigned
               the input visibility weight.

CONTEXT
-------
Before interferometer data can be processed, it must be read into
difmap. The observe command reads interferometer data in the form of
single source UV FITS files. The older Caltech VLBI merge format files
are no longer acceptible. The caltech VLBI package program 'MERGEFITS'
may be used to convert merge files to FITS.

UV FITS files do not provide any means to map visibilities on
different baselines into integrations. Each visibility has its own
time-stamp, which need not aggree with those on other baselines within
the same logical integration. In fact UV FITS files do not even limit
visibilities on different baselines to have the same integration
time. Difmap, on the other hand does require that visibilities be
grouped into integrations. This is the reason for the 'binwid'
argument of the 'observe' command. If the visibilities do not lie on
an integration grid then you must specify a suitable integration time
into which visibilities should be binned into integrations. Depending on
how the FITS file has been processed, it may already have visibilities
grouped into integrations with identical time-stamps assigned to each
grouped visibility, in which case no 'binwid' argument will be
required. This is the case for files written by difmap. If you do not
know what state your file is in, then try to read it with the observe
command without specifying an integration time. Then if 'observe'
reports something along the following lines, then either run the
'uvaver' command to re-grid the data or equivalently re-run the
observe command with a suitable integration time.

observe poor_sampling.uvf
...
Apparent sampling: 0.245305 visibilities/baseline/integration.
*** This seems a bit low - see "help observe" on the binwid argument.
...
```

Other symptoms of in-completely binned integrations are that selfcal flags all of your data due to the lack of closure quantities, and that station based editing in vplot behaves like baseline based editing.

While the 'binwid' and 'scatter' options are provided primarily as a mechanism to group data into integrations, they may also be employed to average ones data to longer integration times for efficiency reasons. The effect is identically equivalent to reading the data with observe and then running the 'uvaver' command with the same arguments, except that in the latter case you might not have sufficient memory to read the data before averaging and reading in the larger file would take longer.

LIMITATIONS

Only single source, time-ordered UV FITS files will be accepted by difmap. Multi-source files must be split into one or more single source files before presenting them to difmap. AIPS provides the SPLIT task to do this. Similarly, AIPS UVSRT may be used to re-sort files into time order (eg. TB order).

Difmap accepts multiple sub-arrays within a file, multiple polarizations, spectral-line channels and multiple IFs.

While difmap does accept multiple IFs, it does not make any allowances for spectral-index effects over the range of frequencies covered by the IFs. If the source structure changes significantly between IFs, you should SPLIT the IFs into separate files and process them independantly within difmap. Also note that difmap requires that the frequencies assigned to each IF do not change over the duration of the file. To enforce this difmap rejects files containing multiple frequency IDs.

SIDE EFFECTS

Any previously read UV data will be discarded before the new file is read. Any existing models and CLEAN windows will also be discarded. All weight options are restored to their defaults.

The current map-grid will be cleared, but its dimensions and cell-size will not be changed.

RELATED COMMANDS
---
wobs - Write out a modified UV FITS file.
select - Select a polarization and channels to be processed.
uvaver - Used to re-grid UV data.

peak

```
Return details of the min,max or absolute max flux in a map.

  peak attribute, pixel_type

EXAMPLE
-------
1. Display the min,max and absolute max flux in the current map.

 0>pr peak(flux,min),peak(flux,max),peak(flux,abs)
 -0.543233 3.44326 3.44326
 0>

2. Shift the phase-center to that of the map pixel that contains the
   max absolute flux to the center of the map.

 0>shift -peak(x),-peak(y)
 shift: Shifting UV data, clean models and windows by: 20 (mas) East
 shift: Shifting UV data, clean models and windows by: -20 (mas) North
 0>

PARAMETERS
----------
attribute  -  The name of the attribute of the selected pixel to be
              returned by the function.
              Possible values are:
               flux -  The flux of the selected pixel.
               x    -  The X-axis position of the pixel.
               y    -  The Y-axis position of the pixel.

pixel_type -  Default = abs
              The name of the type of pixel to return the details of.
              Possible values are:
               abs  -  The pixel with the max absolute flux in the map.
               min  -  The pixel with the min flux in the map.
               max  -  The pixel with the max flux in the map.

CONTEXT
-------
peak() is a function that returns details about one of two specific
pixels of the current residual or clean map. The two pixels are, the
pixel having the mininum flux in the map, and the pixel having the
maximum flux in the map. In addition, one of these pixels has a higher
abolute flux than the other, and requesting the pixel with the max
absolute flux will return details about this pixel.

The selectable attributes of the requested pixel are its (signed)
flux, and its X and Y axis positions with respect to the center of the
map, all measured in map units.
```

```
SIDE EFFECTS
------------
If the map is not up to date, then it will be inverted before a value
is returned.

RELATED FUNCTIONS
-----------------
mapvalue - Return the value of the map pixel closest to a given position.
imstat   - Return image plane map statistics.
```

peakwin

```
Place a CLEAN window around the brightest pixel in the residual map.

  peakwin size, doabs

EXAMPLE
-------

0>peakwin
Added new window around map position (2, -2).
0>

PARAMETERS
----------

size   -   Default = 1.0
           The relative size of the clean window with respect to the
           aspect of the clean beam.

doabs  -   Default = false
           By default the clean window will be placed around the pixel
           with the maximum flux. However, if doabs=true then the clean
           window will be placed around the pixel with the maximum
           absolute value in the map. The latter could be useful for
           spectral line mapping of absorption features.

CONTEXT
-------
This command is provided as a primitive for automatic mapping scripts,
where CLEAN windows need to be set non-interactively. The command
looks at the position of the brightest pixel in the residual map, and
if it is not already enclosed in a CLEAN window, adds a new CLEAN
window centered upon it. The added window has the dimensions of the
rectangular area that just encloses the ellipse of the CLEAN beam last
estimated by the 'invert' command, scaled by the optional 'size' argument.

SIDE EFFECTS
------------
If the residual map and/or beam is not up to date when this function
is called, the 'invert' command will be invoked.
```

projplot

Plot visibility amplitudes and/or phases versus projected UV distance.

```
  projplot angle, station, uvmin, uvmax, ampmin, ampmax, phsmin, phsmax, docursor
```

```
EXAMPLE
-------

0> projplot 45
0>
```

This example plots baseline amplitude and phase versus UV distance along a radial line 45 degrees North through East. Model data if present is plotted in red. If the display device has a cursor then interactive mode will be invoked after the initial display has been completed.

```
PARAMETERS
----------

angle     -   (Optional: default = 0.0)
              The angle of the radial line along which the UV distance
              is to be measured, given in degrees North through East.

station   -   (Optional) The name of a station to highlight in the
              plot. If not given or given as an empty string "", no
              station will initially be highlighted. (Stations
              can be specified subsequently with the cursor).

uvmin     -   (Optional) Default=0.
              The minimum UV radius to display.
      Unless changed with the mapunits command, the units are
              millions of wavelengths.

uvmax     -   (Optional) Default=0. (0 specifies the whole range).
              The maximum UV radius to display.
      Unless changed with the mapunits command, the units are
              millions of wavelengths.

ampmin    -   (Optional) Default=0.
              The minimum amplitude to display.

ampmax    -   (Optional) Default=0.
              The maximum amplitude to display.
              If you want to set later arguments while keeping the
              default amplitude range set both ampmin and ampmax
              to 0.

phsmin    -   (Optional) Default=-180.
```

```
              The minimum phase to be displayed (degrees).

phsmax    -   (Optional) Default=+180.
              The maximum phase to be displayed (degrees).
              If you want to set later arguments while keeping the
              default amplitude range set both phsmin and phsmax
              to 0.

docursor  -   (Optional) Default=TRUE.
              If the display device has a cursor but you don't want
              to enter the interactive cursor mode, make this FALSE.

CONTEXT
-------
This command is almost identical to the radplot command, except that
rather than displaying data versus radial distance from the orgin,
projplot displays the same data versus the UV distance parallel to a
given position angle. This is useful for the class of sources that
are dominated by structure along a given position angle. Such sources
include double sources and sources with linear jets. When projplot is
used to plot such data at the same position angle as the dominant
source structure then its effectively 1-dimensional structure is
revealed. In particular, for a double source, when the projection
angle in projplot matches the position angle of the line connecting
the two sources, you should see decaying cos-squared fringes in the
amplitude plot and a linear ramp in phase. Setting the projection
angle accurately is essential to seeing such structure, so projplot
provides interactive angle increment and decrement keys to help search
for the best angle (see below). Apart from the obvious educational and
esssthetic uses of such a display, when used with linearly oriented
structures, projplot has the advantage over radplot of displaying data
in a less messy form in which bad data can more easily be identified.

INTERACTIVE MODE
----------------
If your display device has a cursor, then there are a number of
interactive options that you can use. These are selected by moving the
cursor into the plot window, and pressing the following keys:


   X - Quit the projplot session, and return to the difmap prompt.

   L - Re-display the plot.

   . - Toggle the marker symbol used to display the data between the
       smallest available and the next largest. By default
       the smallest possible marker symbol is used for speed, but if
       if the data are sparse then the larger marker symbol may be more
       convenient.
```

H - (Help) Briefly list all keyboard options.

n - Highlight visibilities from the next telescope in the currently highlighted sub-array. Initially no telescope is highlighted. If this key then pressed, the visibilities of the first telescope of the first sub-array will be highlighted. Pressing this key again highlights the second telescope, etc.. When the last telescope of the current sub-array has been plotted, the first telescope of the next sub-array will be plotted. So by repeatedly pressing this key you will eventually have seen each telescope of all sub-arrays individually highlighted.

p - This has the reverse the effect to the 'n' key, highlighting the visibilities of the previous telescope in the current sub-array, and wrapping back to the last telescope in the previous sub-array, after the first telescope of the current sub-array is highlighted.

N - [Upper-case n] Similar to the lower-case 'n' key this key results in the first telescope of the next sub-array in the observation to be highlighted. In this way you can jump between sub-arrays without having to see all the telescopes of the intermediate sub-arrays highlighted one at a time.

P - [Upper-case p] This has the reverse effect of the 'N' key, allowing one to directly step backwards through sub-arrays.

T - To have a specific telescope of a specific sub-array highlighted without having to step through all the intermediate telescopes and sub-arrays, press this key. On the text window you will then be prompted for the name of the telescope to be highlighted. Telescopes are specified by an optional sub-array number delimited by a colon, followed by an unambiguous telescope name prefix. If the sub-array number and colon are omitted then the sub-array from which telescopes are currently being highlighted will be assumed. For instance, both 3:BONN and BON refer to a telescope named BONN in sub-array 3 if another telescope of sub-array 3 is currently being highlighted. Also, provided that sub-array 2 does not contain more than one telescope starting with the prefix JBN, 2:JBN is sufficient to refer to a telescope called JBNK1 in sub-array 2.

S - This key invokes a report on the baseline and time of the nearest point to the cursor. The result is displayed on your terminal. The actual data point is unaffected.

A - This key (left-mouse-button) flags the nearest data-point to to the cursor. Note that the preferred method for editing points is through the vplot command in station editing mode. Individual points should only be flagged in projplot if they

are clearly singled out as being extremely bad, as opposed to being part of a group of bad points manifesting a bad telescope. If you delete too many points singly, rather than by station you may find that subsequent self-calibration will produce wild solutions due to incomplete or ambiguous un-connected closure triangles.

C - This initiates cut area selection, through which a rectangular area may be selected within which to flag data. After pressing 'C' you will be expected to enter the locations of two opposite corners of the area, by pressing 'A' (left-mouse-button) over the corresponding points of the plot. To cancel a half selected area press 'D' (central-mouse-button). Once two corners have been selected, all visibilities displayed in that area will be flagged and will then disappear from the plot.

W - Toggle spectral-line based editing. By default, edits are applied to all polarizations over the range of spectral-line channels requested in the last use of the 'select' command. The 'W' key toggles between applying edits to the currently selected spectral-line channels, and to all spectral-channels. The mode line above the plot shows the spectral-line channel range being edited.

U - Select a new UV-distance display range. Having pressed this key, you will be expected to either press it a second time to select the full available UV-distance range (and enable future autoscaling), or to select a new range by pressing the 'A' key twice, once at each of the two UV-radii that enclose the desired range. To abort the selection press the 'D' key (middle mouse button) and the display will remain unchanged.

Z - Select a new amplitude or phase display range. Having pressed this key, you will be expected to either press it a second time to select the full available amplitude and phase ranges (and enable future autoscaling), or to select a new range by pressing the 'A' key twice, once at each of the two amplitudes or phases that enclose the desired range. To abort the selection press the 'D' key (middle mouse button) and the display will remain unchanged.

Keys used to interactively change the projection angle:

? - If you press this key then in the terminal window that you invoked projplot from, you will be prompted to enter a new projection angle in degrees. Having done so the display will be updated for the new projectio angle.

< - This key decrements the currently selected projection angle by 5 degrees and then updates the display for the new angle.

```
  >  - This key decrements the currently selected projection angle by
       5 degrees and then updates the display for the new angle.

Display mode options. The following keys each change how the data are
displayed. In order that you can change more than one attribute at a
time, they may be grouped by pressing one key after the other. When
you have speficied all the attributes that you want to, press the RETURN
key and the display will be refreshed.

  M  - This key toggles whether the model is plotted. Model
       amplitudes/phases are plotted as red dots.

  1  - Only display amplitudes versus UV radius.

  2  - Only display phases versus UV radius.

  3  - Display both amplitudes and phases in vertically adjacent plots.

  +  - This key toggles whether the cursor is shown as a small cross or
       as a cross-hair that extends the full width and height of the
       display. Currently only the /xserve and /xwindow PGPLOT devices
       support this feature.

CONFIGURATION VARIABLES
-----------------------
The display-mode option keys listed above may be preset in the
variable, 'pflags'. If pflags is an empty string, "", then the default
option string "m3" is substituted. This requests that the othrwise
optional plotting of the model be selected by default and that both
amplitudes and phases be displayed. To override this default and have
projplot start up by displaying just amplitudes, on the command line
one would type:

0> pflags="m1"

If you always want to override the default, then place such an
assignment line in your difmap login file (the file named in the
optional DIFMAP_LOGIN environment variable).

OTHER DISPLAY COMMANDS
----------------------
radplot  -   Display visibilities amp/phase vs. UV radius.
uvplot   -   Display the sampling of the UV plane.
vplot    -   Display observed and model visibilities from the current IF.
tplot    -   Display the time-sampling of each telescope of the current IF.
corplot  -   Display the self-cal corrections of the current IF.
cpplot   -   Display observed and model closure phases interactively.
```

radplot

```
Plot visibility amplitudes and/or phases versus UV radius.

  radplot station, uvmin, uvmax, ampmin, ampmax, phsmin, phsmax, docursor

EXAMPLE
-------

0> radpl "BONN"
0>

This example plots baseline amplitude against UV radius, plotting all
but the data in the first sub-array associated with BONN in green.
BONN data is plotted in a different color to highlight it. Model data
if present is plotted in red. If the display device has a cursor then
interactive mode will be invoked after the initial display has been
completed.

PARAMETERS
----------

station   -   (Optional) The name of a station to highlight in the
              plot. If not given or given as an empty string "", no
              station will initially be highlighted. (Stations
              can be specified subsequently with the cursor).

uvmin     -   (Optional) Default=0.
              The minimum UV radius to display.
      Unless changed with the mapunits command, the units are
              millions of wavelengths.

uvmax     -   (Optional) Default=0. (0 specifies the whole range).
              The maximum UV radius to display.
      Unless changed with the mapunits command, the units are
              millions of wavelengths.

ampmin    -   (Optional) Default=0.
              The minimum amplitude to display.

ampmax    -   (Optional) Default=0.
              The maximum amplitude to display.
              If you want to set later arguments while keeping the
              default amplitude range set both ampmin and ampmax
              to 0.

phsmin    -   (Optional) Default=-180.
              The minimum phase to be displayed (degrees).

phsmax    -   (Optional) Default=+180.
```

```
               The maximum phase to be displayed (degrees).
               If you want to set later arguments while keeping the
               default amplitude range set both phsmin and phsmax
               to 0.

docursor  -    (Optional) Default=TRUE.
               If the display device has a cursor but you don't want
               to enter the interactive cursor mode, make this FALSE.

CONTEXT
-------
This task is useful for getting an over-all look at the whole data
set in one plot. By default it plots the amplitude of visibilities
of all IFs versus radial distance from the origin of the UV plane.
Optionally it can also be used to display visibility phases instead or
in addition to the plot of amplitudes. See below for details.

For each baseline, one point is plotted per IF. Where multiple
spectral-line channels are selected from a given IF, the visibility
is the average of those channels and is displayed at the corresponding
mean UV radius.

It is often possible to get a vague idea of how the map will appear
from looking at this plot. Unresolved point sources appear as flat
amplitude distributions. Resolved sources display one or more gaussian
fall-off distributions. Multi-component sources beat against each other,
modulating the gaussian fall-off. In some cases you may be able to get
a better impression by running the alternate 'projplot' command. See
help projplot for details.

If the distribution is reasonably smooth, it is also possible to
see the effects of poor calibration. The highlighting function is
invaluable here. Highlighting each station in turn will eventually
reveal the identity of a bad station or baseline. The 'S' option key
described below provides a more direct way of identifying the origin
of discrepant points.

INTERACTIVE MODE
----------------
If your display device has a cursor, then there are a number of
interactive options that you can use. These are selected by moving the
cursor into the plot window, and pressing the following keys:


   X - Quit the radplot session, and return to the difmap prompt.

   L - Re-display the plot.

   . - Toggle the marker symbol used to display the data between the
       smallest available and the next largest. By default
```

the smallest possible marker symbol is used for speed, but if if the data are sparse then the larger marker symbol may be more convenient.

H - (Help) Briefly list all keyboard options.

n - Highlight visibilities from the next telescope in the currently highlighted sub-array. Initially no telescope is highlighted. If this key then pressed, the visibilities of the first telescope of the first sub-array will be highlighted. Pressing this key again highlights the second telescope, etc.. When the last telescope of the current sub-array has been plotted, the first telescope of the next sub-array will be plotted. So by repeatedly pressing this key you will eventually have seen each telescope of all sub-arrays individually highlighted.

p - This has the reverse the effect to the 'n' key, highlighting the visibilities of the previous telescope in the current sub-array, and wrapping back to the last telescope in the previous sub-array, after the first telescope of the current sub-array is highlighted.

N - [Upper-case n] Similar to the lower-case 'n' key this key results in the first telescope of the next sub-array in the observation to be highlighted. In this way you can jump between sub-arrays without having to see all the telescopes of the intermediate sub-arrays highlighted one at a time.

P - [Upper-case p] This has the reverse effect of the 'N' key, allowing one to directly step backwards through sub-arrays.

T - To have a specific telescope of a specific sub-array highlighted without having to step through all the intermediate telescopes and sub-arrays, press this key. On the text window you will then be prompted for the name of the telescope to be highlighted. Telescopes are specified by an optional sub-array number delimited by a colon, followed by an unambiguous telescope name prefix. If the sub-array number and colon are omitted then the sub-array from which telescopes are currently being highlighted will be assumed. For instance, both 3:BONN and BON refer to a telescope named BONN in sub-array 3 if another telescope of sub-array 3 is currently being highlighted. Also, provided that sub-array 2 does not contain more than one telescope starting with the prefix JBN, 2:JBN is sufficient to refer to a telescope called JBNK1 in sub-array 2.

S - This key invokes a report on the baseline and time of the nearest point to the cursor. The result is displayed on your terminal. The actual data point is unaffected.

A - This key (left-mouse-button) flags the nearest data-point to to the cursor. Note that the preferred method for editing points is through the vplot command in station editing mode. Individual points should only be flagged in radplot if they are clearly singled out as being extremely bad, as opposed to being part of a group of bad points manifesting a bad telescope. If you delete too many points singly, rather than by station you may find that subsequent self-calibration will produce wild solutions due to incomplete or ambiguous un-connected closure triangles.

C - This initiates cut area selection, through which a rectangular area may be selected within which to flag data. After pressing 'C' you will be expected to enter the locations of two opposite corners of the area, by pressing 'A' (left-mouse-button) over the corresponding points of the plot. To cancel a half selected area press 'D' (central-mouse-button). Once two corners have been selected, all visibilities displayed in that area will be flagged and will then disappear from the plot.

W - Toggle the scope of edits with respect to spectral-line channels. Each point in the plot comes from a single IF, and its UV radius in the plot is determined by the mean frequency of the channels currently selected from that IF. By default, if you select such a point to be flagged, then all spectral-line channels of the source IF will be flagged, irrespective of the channels which actually went into making the plot. The alternative is to edit just the channels that went into making the plot. The 'W' key toggles which of the two options is used, and a mode line above the plot describes which option is currently in effect.

U - Select a new UV-radius display range. Having pressed this key, you will be expected to either press it a second time to select the full available UV-radius range (and enable future autoscaling), or to select a new range by pressing the 'A' key twice, once at each of the two UV-radii that enclose the desired range. To abort the selection press the 'D' key (middle mouse button) and the display will remain unchanged.

Z - Select a new amplitude display range. Having pressed this key, you will be expected to either press it a second time to select the full available amplitude range (and enable future autoscaling), or to select a new range by pressing the 'A' key twice, once at each of the two amplitudes that enclose the desired range. To abort the selection press the 'D' key (middle mouse button) and the display will remain unchanged.

Display mode options. The following keys each change how the data are displayed. In order that you can change more than one attribute at a

```
time, they may be grouped by pressing one key after the other. When
you have speficied all the attributes that you want to, press the RETURN
key and the display will be refreshed.

  M  - This key toggles whether the model is plotted. Model
       amplitudes/phases are plotted as red dots.

  1  - Only display amplitudes versus UV radius.

  2  - Only display phases versus UV radius.

  3  - Display both amplitudes and phases in vertically adjacent plots.

  +  - This key toggles whether the cursor is shown as a small cross or
       as a cross-hair that extends the full width and height of the
       display. Currently only the /xserve and /xwindow PGPLOT devices
       support this feature.


CONFIGURATION VARIABLES
-----------------------
The display-mode option keys listed above may be preset in the
variable, 'rflags'. If rflags is an empty string, "", then the default
option string "m1" is substituted. This requests that the othrwise
optional plotting of the model be selected by default and that only
amplitudes be displayed. To override this default and have radplot
start up by displaying both amplitudes and phases, on the command line
one would type:

0> rflags="m3"

If you always want to override the default, then place such an
assignment  line in your difmap login file (the file named in the
optional DIFMAP_LOGIN environment variable).

OTHER DISPLAY COMMANDS
----------------------
projplot -   Display visibilities amp/phase vs. projected UV distance.
uvplot   -   Display the sampling of the UV plane.
vplot    -   Display observed and model visibilities from the current IF.
tplot    -   Display the time-sampling of each telescope of the current IF.
corplot  -   Display the self-cal corrections of the current IF.
cpplot   -   Display observed and model closure phases interactively.
```

resoff

```
Determine and apply a baseline based amplitude and phase correction.

  resoff baseline_name

EXAMPLE
-------

To correct for correlator offsets on baseline BONN-WSRT of the first
subarray.

  0> resoff "BON-WSRT"
  1:BONN-WSRT: 0.945151 amplitude change, -0.399408 degrees phase offset
  0>

To correct for correlator offsets on baseline HSTK-OVRO of the 3rd
sub-array.

  0> resoff 3:HSTK-OVRO
  3:HSTK-OVRO: 0.988347 amplitude change, -3.50419 degrees phase offset
  0>

To correct all baselines of sub-array 2.

  0> resoff 2
  2:WSRT-JBNK: 0 amplitude change, -5.63816 degrees phase offset
  2:WSRT-BOLOGNA: 0 amplitude change, 13.0693 degrees phase offset
  2:WSRT-HSTK: 0 amplitude change, -0.687232 degrees phase offset
  2:JBNK-BOLOGNA: 0 amplitude change, 12.97 degrees phase offset
  2:JBNK-HSTK: 0 amplitude change, 2.05668 degrees phase offset
  2:BOLOGNA-HSTK: 0 amplitude change, 2.33325 degrees phase offset

To correct all baselines.

  0> resoff
  1:BONN-WSRT: 0.945151 amplitude change, -0.399408 degrees phase offset
  .....etc....

PARAMETER
---------
baseline_name  -  Default=""
                  The name of the baseline(s) to be corrected. See the
                  antenna_names help topic for a discussion of the
                  syntax and interpretation of baseline specification
                  arguments.

CONTEXT
-------
The use of this command is NOT recommended except in exceptional
```

circumstances. The only recommended use of this command is for inspection to determine whether a data-set contains closure offsets with respect to a given model - in which case it should be followed by clroff to remove the closure offsets instated. In very high dynamic range mapping it can be used to fix baseline dependent amplitude and phase "non-closing" errors. On other data-sets it is just as likely to introduce new non-closing errors and should not be used.

resoff should only be used after all possible cleaning and self-calibration has been performed and then only when the data appear to fit very well on all but one or two baselines. Visual inspection of the data is essential before embarking on this coarse, so use the vplot and radplot commands first. If the miscreant baselines are short baselines, then the real cause of the errors is undoubtedly an incomplete model, possibly due to insufficient sampling at short UV spacings. In such cases use of resoff is not justified.

resoff determines and applies a single amplitude and phase correction for the requested baseline. The amplitude correction is determined as the ratio of the weighted means of the model and observed amplitudes on the requested baseline, over the whole observation. The phase correction is the weighted mean phase difference between the model and observed phases over the same range.

Be warned, unlike self-calibration, resoff is not constrained by any closure or other constraints. It will always make a map look more like the model but at the expense of reality if the model isn't correct.

SIDE EFFECTS

Resoff establishes the latest clean model when necessary. It also invalidates the current residual map, which will be re-calculated by the next command that needs it.

RELATED COMMANDS
---
clroff - Undo the effects of all resoff commands in this difmap session.

restore

```
Add the CLEAN model to the residual map to form a clean map.

  restore bmin, bmaj, bpa, omit_residuals, do_smooth

EXAMPLE
-------

0>restore 1.8, 6.1, 27
Restoring with beam: 1.8 x 6.1 at 27 degrees (North through East)
Clean map  min=-0.050992  max=3.324691 Jy/beam
0>

All but the first line are responses from the 'restore' command and
the client commands that it calls.

PARAMETERS
----------
bmin            -  The minor axis full-width-at-half-maximum of the
                   restoring beam (clean beam). Unless changed with
                   the mapunits command, the units are milli-arcsec.
                   If this is the only parameter specified then a
                   circular beam with bmaj=bmin and bpa=0 will be
                   assumed.

bmaj            -  The major axis full-width-at-half-maximum of the
                   restoring beam (clean beam). Unless changed with
                   the mapunits command, the units are milli-arcsec.

bpa             -  The position angle of the beam measured from north
                   going towards east. ie. a positive angle denotes an
                   anti-clockwise rotation on the map when displayed
                   by 'mapplot'. If this argument is omitted then 0
                   will be assumed.

omit_residuals  -  Default = false
                   Normally the clean model is superposed on top of
                   the residual map. Alternatively the residual map
                   can be omitted by specifying a value of true for
                   the omit_residuals argument. The result will be an
                   image of the clean model.

do_smooth       -  Default = true
                   By default the residual map is smoothed with a
                   gaussian of width 3x3 pixels before the clean model
                   is added to it. This is a common way of
                   compensating for the fact that the model is
                   convolved with a smooth gaussian beam, while the
                   residual noise is convolved with the dirty beam. To
```

```
                    prevent this behavior specify a value of false for
                    the do_smooth argument.

If no parameters are specified 'restore' will either use the values
that were given to it the previous time it was invoked, or if the
weighting used by invert has been changed since the last 'restore',
'restore' will use the estimated beam size from the last time that
'invert' inverted the beam. Commands that force 'restore' to discard
the previous beam parameters and use the estimate from invert,
include: observe, uvtaper, uvrange, uvzero, uvweight.

To force restore to fall back on the estimated beam size generated by
the last invert, type

0> restore 0

Examples are:

0> restore 0   Always restores with the latest estimate from 'invert'.

0> restore     Uses whatever restore used last time unless the dirty
               beam produced by invert has been changed by changes in
               weigthing etc..

0> restore 1.5,3.2,-10.5   Restores with an elliptical beam of
                           bmin=1.5, bmaj=3.2 at -10.5 degrees.

0> restore 1.5      Restores with a circular beam of size 1.5.

0> restore 1.5,3.2  Restores with an ellipse of major-axis position angle 0.


CONTEXT
-------
This is usually the final step in mapping a source. It can also be done
at any time while mapping, but since it over-writes the current
residual map you will incur the overhead of re-inverting the UV data
on the next clean.

Restore generates an image of the CLEAN-model components convolved
with an elliptical gaussian beam and adds this to the current residual
map. This is the final map.

After restoring the map, it may be displayed with mapplot (the first
argument to mapplot must be cln). 'mapplot' allows contours to be plotted
on restored maps and will also plot a shaded representation of the
restoring beam in one corner.

For example:
```

```
0> mapplot cln
```

This plots the restored map. Note that if the map isn't restored when you type this or the UV data has been changed since you restore'd, mapplot will call restore for you with no arguments. Also note that if you neglect to write cln as the first argument to mapplot, then mapplot will assume that you want to plot the residual map and will re-invert it for you - take care!

SIDE EFFECTS

Since the restored map over-writes the residual map array, the residual map is thereafter useless for continued cleaning and will be re-inverted by the next clean. This saves memory at the expense of CPU time.

rmodel

```
Read a new CLEAN model from a VLBI model file.

  rmodel file_name, do_continuum

EXAMPLE
-------

0>rmodel test.mod
A total of 26 model components were read from file test.mod
0>

PARAMETERS
----------
file_name    - The name of an existing model file.

do_continuum - (Default=false)
               If omitted or given as FALSE, the contents of the model
               file will supersede the established and tentative
               models. If it is given as TRUE, then the contents will
               be used to supersede the continuum model.

CONTEXT
-------
There are at least two reasons why one might want to read in an external
a model file. The first is to provide a starting model for
self-calibration - this is best done using the 'startmod' command. The
second is to let one re-start mapping where one left off at an earlier
date.

A third reason that is relevant to spectral-line work, is to read in a
model from a separate observation of the continuum underlying a
spectral-line source. The model produced by the continuum observation
can then be used as a model to be subtracted prior to spectral-line
mapping. See the 'setcont' command for further details.

SIDE EFFECTS
------------
The models read supersede any existing models of the same type. Thus,
if do_continuum is FALSE, the current established and tentative models
will be discarded before reading the new model. If do_continuum is TRUE,
then the current continuum model will be discarded before reading the
new model. So, if you wish to retain these models for later, remember
to use the wmodel command before using rmodel.

RELATED COMMANDS
----------------
startmod - Self-calibrate an observation with a temporary point-source
           model.
```

```
wmodel   - Write clean models to a VLBI model file.
save     - Save all data files and the difmap running parameters.
```

rwins

Read windows previously saved CLEAN windows from a text file.

```
  rwins winfile
```

EXAMPLE

```
0>rwins "myfile.win"
rwins: Read 9 windows from myfile.win
0>
```

PARAMETERS
----

winfile - The name of a file containing previously saved windows.

CONTEXT

CLEAN windows are set interactively in mapplot and/or directly via the addwin command. The resulting list of windows may be saved in a file using the 'wwins' command and retrieved later using the 'rwins' command. This makes it possible to use the same windows for data at a different epoch or to continue cleaning a data-set at a later date using the same windows.

The window file is a text file. Each line in the text file corresponds to a single CLEAN window and should contain 4 numbers separated by spaces. The first two numbers specify the relative Right-Ascension of the two vertical window edges (either one first) wrt the center of any map. The second two specify the relative Declination of each horizontal window edge (either one first) wrt the center of any map. All positions are measured in milli-arcseconds and use the same sign conventions as displayed by the mapplot command.

SIDE EFFECTS

Any existing list of windows will be deleted before reading from the file.

RELATED COMMANDS
----

wwins - Write CLEAN windows to a text file.

save

Save UV data, models, windows, the restored map and a command file.

```
  save prefix_name
```

EXAMPLE

```
0>save "3c345"
Writing UV FITS file: 3c345.uvf
Writing 94 model components to file: 3c345.mod
wwins: Wrote 3 windows to 3c345.win
Writing map to FITS file: 3c345.fits
Writing difmap environment to: 3c345.par
0>
```

PARAMETERS
----

prefix_name - The prefix to give all the output file names - see the example above.

STANDARD SUFFIXES

To the prefix name that you enter the following extensions are appended to indicate the file type:

.uvf - The suffix for the UV FITS data file.
.mod - The suffix for any model file.
.win - The suffix for any windows file.
.fits - The suffix for any restored map fits file.
.par - The command-file containing commands to restore the running parameters and data-files into difmap on a later occasion.

CONTEXT

Before leaving difmap it is important to save all processed data, unless the data is to be discarded. The 'save' command provides a convenient method for saving all relevant data with a single command. It also now saves the running parameters in a command file.

'save' calls the wobs, wmodel, wwins and wmap commands for you where appropriate, to save the UV data, any models, any windows and any restored map that has or can be created. Note that if necessary, when there is a model to restore with, the map will be restored for you.

The 'save' command also writes a command file that may be used to

```
restore the files and difmap state at a later date.

There are now two methods for reading the data back into difmap at a
later date. Originally the 'get' command was provided for this
purpose, but the get command could only restore the data files - it
did not restore the running parameters. Now the save command has been
modified to create an extra file - the .par file. This is a command
file that contains commands to restore the data files into difmap AND
to restore the running parameters.

Thus the preferred method for retrieving the state of difmap at a
later date, is to execute this command file.

In the example given above a file 3c345.par was created. To restore
the files and running parameters at a later date one would type:


0>@3c345.par

The response in this case would be somthing like:

Reading UV FITS file: 3c345.uvf
The integration time appears to be 1.31321 seconds.
There appear to be 485 integrations.
AN table 1: 485 integrations on 55 of 55 possible baselines.
Found source: 3C345

Number of spectral-line channels: 1

IF    Freq (Hz)  Chan BW (Hz)  Full BW (Hz)  Sideband
01  1.66299e+09         2e+06         2e+06       USB

Polarization(s): RR

Read 192 lines of history.

Reading an estimated 26675 visibilities.
Selecting channels: 1 -> 1, polarization: RR.
A total of 94 model components were read from file 3c345.mod
rwins: Read 3 windows from 3c345.win
New map grid = 256x256 pixels with 0.5x0.5 milli-arcsec cellsize
Gaussian UV-taper cancelled
UV range cancelled
New uniform weighting binwidth=2 pixels
Amplitude error weighting cancelled
Radial weighting cancelled
Zero-baseline flux cancelled
Self-cal gaussian UV-taper cancelled
Amplitude corrections will not be limited
Phase corrections will not be limited
```

```
The mapplot display area will be limited to:
 Relative  RA: (The whole available range)
 Relative DEC: (The whole available range)
- In phase-only self-cal, good data on baselines that are not in closed
  arrays of at least 3 telescopes will be flagged.
- In amplitude self-cal, good data on baselines that are not in closed
  arrays of at least 4 telescopes will be flagged.
0>
```

These are the output lines of the various commands that were run from the command file.

RELATED COMMANDS

```
get    - Restore UV data, models and windows from files.
wobs   - Write the UV data to a UV FITS file.
wmodel - Write the CLEAN model to a (text) VLBI model file.
wmap   - Save the restored map as a FITS file.
wbeam  - Save the dirty-beam as a FITS file.
wwins  - Write CLEAN windows to a text file.
exit   - Exit calls save if so requested.
```

scangap

```
Change the time gap used to delimit neighboring scans.

  scangap gap, sub_array

EXAMPLES
--------

1. To assign a 30 minute scan separator to all sub-arrays:

   0>scangap 30*60
   Delimiting interscan gap changed to 1800 seconds in all sub-arrays.
   0>

2. To re-instate the default (1 hour) separator:

   0>scangap 0
   Delimiting interscan gap changed to 3600 seconds in all sub-arrays.
   0>

3. To assign a 20 minute scan separator only to sub-array 2:

   0>scangap 20*60, 2
   Delimiting interscan gap changed to 1200 seconds in sub-array 2.
   0>

4. To see what the current gaps are set to, omit all arguments:

   0>scangap
   The delimiting interscan gap is 3600 seconds in sub-array 1.
   The delimiting interscan gap is 1200 seconds in sub-array 2.
   0>

PARAMETERS
----------

gap        -   The new interscan gap to assume. This is the minimum
               time separation between neighboring integrations at which
               integrations are taken to occupy different scans.
               When an observation is first read into difmap, all
               sub-arrays are assigned a scan delimiter of 3600
               seconds (1 hour). This default may be re-selected by
               giving 'gap' as 0, as in the second example above.

sub_array  -   Optional: Default=0
               If this argument is not provided, or is given as 0,
               then the new scan delimiter is assigned to all
               sub-arrays. Otherwise, the number given specifies the
               sub-array to which the scan separator should be
```

assigned.

CONTEXT

All difmap plotting commands that plot anything versus time, offer
the option of resolving the data into multiple isolated scans. These
scans are then plotted side by side with the intervening gaps removed.
The plotting commands also know not to extend model lines between
scans, even when scan mode is not in effect.

In order to decide what constitutes a scan, difmap simply says that
any two integrations that are separated by more than a given amount of
time mark the end of one scan and the start of a new scan. By default
this time interval is one hour, and is a good choice for most
observations. Somethines the default is not the correct choice, and
the 'scangap' command gives you the opportunity to change the default,
either on a sub-array by sub-array basis, or globally for all
sub-arrays.

Note that no more than 20 scans per sub-array are allowed. This means
that if too short an interval is requested, the command will emit an
error message ignore the requested interval.

RELATED COMMANDS
----
vplot   -   Display observed and model visibilities from the current IF.
tplot   -   Display the time-sampling of each telescope of the current IF.
corplot -   Display the self-cal corrections of the current IF.
cpplot   -   Display observed and model closure phases interactively.

select

Select a polarization and ranges of spectral-line channels to be processed.

```
  select polarization, ca, cb, ...
```

EXAMPLES

1. Select visibilities of polarization I over two inclusive spectral-line channel ranges.

```
0>select I, 20, 25, 47, 65
Selecting polarization: I,  channels: 20..25 47..65
Reading IF 1 channels: 20..25 47..65
0>
```

2. Select continuum channels either side of a spectral-line feature that occupies the range 21 to 60:

```
0>select I, 1, 20, 60, nif*nchan
Selecting polarization: I,  channels: 1..20 60..112
Reading IF 1 channels: 1..20 60..112
0>
```

3. Select channel ranges that span more than one IF. The following example is based on an observation that has three IFs, each of which has 64 channels.

```
0>select i,50,70
Selecting polarization: I,  channels: 50..70
Reading IF 1 channels: 50..64
Reading IF 2 channels: 65..70
Reading IF 3 channels: (none)
0>
```

4. Channel ranges can be given in any order and can overlap. The following example shows that the select command re-organizes ranges into non-overlapping ranges.

```
0>select I, 23,45, 60,70, 25,30, 51,53, 40,50
Selecting polarization: I,  channels: 23..53 60..70
Reading IF 1 channels: 23..53 60..70
0>
```

5. If the last range given is unpaired, then this denotes a range consisting of a single channel.

```
0>select I,10
Selecting polarization: I,  channels: 10..10
```

```
   Reading IF 1 channels: 10..10
   0>


ARGUMENTS
---------

polarization  - (Default = The polarization last selected, or on the
                first call, either I if available, or the first
                recorded polarization.
                The name of a polarization that was recorded in the UV
                FITS file, or one that can be derived from other
                recorded polarizations. Use the 'header' command to
                see which polarizations were recorded.
                Further details are provided below.

ca, cb, ...   - Default = The ranges of a previous selection, or all
                          channels on the first call.
                One or more ranges of spectral-line channels from one
                or more IFs are specified by giving the indexes of the
                first and last channels of each range, using channel
                indexes taken from the set [1..nif*nchan].

                If an odd number of channel indexes is specified, the
                last index is taken to represent a range that contains
                a single channel.

                The select command sorts channel ranges into ascending
                order and coalesces overlapping and contiguous ranges.

CONTEXT
-------
In Difmap, one combination of stokes parameters and spectral-line
channels is mapped at a time.  This combination is known as the
"current processing stream". The 'select' command allows you to
specify the scope of this stream in terms of the polarization to be
processed and one or more ranges of spectral-line channels. Once such
a selection has been made, most difmap commands operate on this data,
rather than the raw data from the UV FITS file. However edits, and
'selfcal' and 'resoff' calibrations are not restricted to the selected
data, and are applied both to the raw data set and to all future
selections.

For example, to map a spectral-line data-set, one would typically
select one or more channels containing strong line-emmission from a
single IF. This would then be mapped, and in the course of doing so,
self-calibration would be applied. The corrections accumulated for the
channels of the selected IF would thereafter be applied to all other
channel selections from that IF, unless the corrections were cleared
with the 'uncal' command. Furthermore, future corrections, based on
```

other spectral-line channels of the same IF, would build upon the existing corrections. This ensures that the relative positions of features in different channels are preserved.

Note that the 'specplot' command is independent of the current processing stream selection. This makes it a convenient way to see what channels to select before using the 'select' command. See also the spectral_line help topic.

POLARIZATION SELECTION

The polarizations recorded in the originating UV FITS file can be displayed with the 'header' command.

The polarization argument may either be one of these polarizations, or be the name of a polarization that can be derived from them.

The names of recognised polarizations are:

I Q U V RR LL RL LR XX YY XY YX

The following is a list of polarizations that may be contructed from other polarizations:

Name	Derived from:	Derived as:
I	RR and LL	(RR + LL)/2
Q	RL and LR	(RL + LR)/2
U	RL and LR	(LR + i.RL)/2
V	RR and LL	(RR - LL)/2

CHANNEL RANGES (and IF ranges)

The channel numbers that the 'select' command understands start at 1, and end with the total number of channels in the observation. When there are multiple IFs, the latter is the sum of the number of channels in all IFs. For specification purposes, channel numbers increase seamlessly from the first IF to the last IF, regardless of the relationship between neighboring IFs and the sign of their inter-channel frequency increments. This is the same convention used by the 'specplot' command, so if you are confused by this, use the 'specplot' command to look at the assignments of channels to IFs.

For example, consider an observation that has two IFs, each with 64 channels. In the example, the 'header' command shows the following assignment of frequencies to the IFs:

There are 2 IFs, and a total of 128 channels:

IF	Channel	Frequency	Freq offset	Number of	Overall IF

```
      origin    at origin  per channel   channels    bandwidth
   ------------------------------------------------------------ (Hz)
   01        1  1.53575e+10       125000         64        8e+06
   02       65  1.53655e+10       125000         64        8e+06
```

In this example channel number 1 refers to the first channel of IF 1 and has a center frequency of 1.53655e+10 Hz, whereas channel number 65 refers to the first channel of IF 2 and has a center frequency of 1.53575e+10 Hz.

Note that when no channels are selected from a given IF, that IF is said to be unsampled, and it will not be processed, apart from the application of global editing. This is essential for spectral-line observations, but can also be used in continuum observations if different IFs must be mapped separately.

Note that continuum observations are treated as spectral-line observations with only one channel per IF. In such cases, the channel numbers are equivalent to IF indexes, and one can then select ranges of IF indexes directly.

IMPLEMENTATION DETAILS

The 'select' command extracts the requested data from a scratch file called uvdata.scr that contains all the raw UV data from the last UV FITS file that was read. For each baseline of each integration, 'select' derives a single visibility per IF. This is formed by vector averaging visibilities of the given polarization, over the given range of spectral-line channels. These visibilities are then stored in another scratch file called ifdata.scr, from which one IF at a time is temporarily paged into memory for display or other processing.

RELATED HELP TOPICS
----

spectral_line - An overview of spectral-line mapping in Difmap.
multi_IF   - An overview of multi-IF mapping in Difmap.

RELATED COMMANDS
----

observe - Read a random-groups UV FITS file.
header   - Use this to see what polarizations, IFs and spectral-line
           channels are available.
specplot - This plots visibility spectra, and provides a convenient
           way to see what channel ranges to select, based upon the
           location of spectral features.

selfant

```
Set antenna based constraints for subsequent self-calibration.

  selfant antenna, dofix, weight

EXAMPLE
-------

0>selfant
1:BONN     self-cal  status=correctable  weight=1
1:WSRT     self-cal  status=correctable  weight=1
1:JBNK1    self-cal  status=correctable  weight=1
1:BOLOGNA  self-cal  status=correctable  weight=1
1:TORUN    self-cal  status=correctable  weight=1
0>
0>selfant bol, true
1:BOLOGNA  self-cal  status=fixed  weight=1
0>
0>selfant jbnk1, false, 2.0
1:JBNK1    self-cal  status=correctable  weight=2
0>
0>selfant
1:BONN     self-cal  status=correctable  weight=1
1:WSRT     self-cal  status=correctable  weight=1
1:JBNK1    self-cal  status=correctable  weight=2
1:BOLOGNA  self-cal  status=fixed  weight=1
1:TORUN    self-cal  status=correctable  weight=1
0>
0>selfant "", false
1:BONN     self-cal  status=correctable  weight=1
1:WSRT     self-cal  status=correctable  weight=1
1:JBNK1    self-cal  status=correctable  weight=2
1:BOLOGNA  self-cal  status=correctable  weight=1
1:TORUN    self-cal  status=correctable  weight=1


All but the lines starting with the 0> prompt are responses from
the selfant command. Each antenna name is prefixed with the number of
its host sub-array. In the above case there is only one sub-array.

PARAMETERS
----------
antenna - (Default="")
          The name of the antenna or antennas to be addressed.
          If this argument is omitted or supplied as "", then
          all antennas will be addressed. See the antenna_names help
          topic for a discussion of the syntax and interpretation of
          antenna specifications.
```

```
dofix   - Normally this should be false. If true then subsequent
          self-calibration will not be allowed to change the complex
          gain of the named antenna. If this argument is omitted no
          change is made to the existing value.

weight  - The relative self-cal weight correction factor to give to
          the named antenna.
          Normally this should be 1.0. This factor expresses the
          degree to which the existing weights on the named antenna
          should be believed with respect to those of other antennas.
          If this argument is omitted no change is made to the
          existing value.

When a new observation is read with the observe command, dofix is
effectively reset to false and weight to 1.0 for all antennas.

CONTEXT
-------
This command effects the way that corrections for specific antennas of
specified sub-arrays are treated during subsequent self-calibration.
Effected commands are selfcal, gscale and startmod.

There are many reasons why preventing the gain of one or more antennas
from being changed is advantageous. On the one hand it constrains the
freedom of solutions of other antennas. This is useful if one has
very few antennas and the antenna that is fixed is an antenna that one
believes to be well calibrated. On the other hand it can be used to
fix the largely unconstrained gains of a very noisy antenna, to
prevent them from going wild.

Each visibility of an observation has an associated weight assigned to
it. Such weights may be indirectly inspected in vplot, where they are
plotted as the equivalent 1/sqrt(weight) error bars. The difmap
self-calibration algorithm uses them to determine the weights to be
used during fitting. If the real uncertainties on all baselines appear
to be equally in error by a constant factor then nothing is lost. But
if the uncertainties on all baselines of a given antenna appear to be
over or under-estimated with respect to those of other antennas then
selfant may be used to specify that appropriately scaled versions of
the weights be used in subsequent self-calibration. This is the
technically correct way to use the 'weight' argument. Sometimes
however, one may decide that the correct weights of a given antenna
are so big compared to other antennas that the resulting self-cal
solutions are dominated by visibilities of this antenna.  In such
cases it may be advantageous to reduce the weight of the good antenna
by specifying 'weight' with a value less than 1.0.

RELATED COMMANDS
----------------
selfcal   - Performs self-calibration.
```

```
selfflag  - Used to control the fate of un-correctable data.
selftaper - Used to down-weight short baselines during selfcal.
selflims  - Used to set limits to amp and phase corrections in selfcal.
gscal     - Calculate overall telescope amplitude corrections.
startmod  - Phase selfcal to a starting model then discard the model.
```

selfcal

```
Self calibrate for telescope phase (and amplitude) corrections.

  selfcal doamp, dofloat, solint

EXAMPLES
-------

1. Phase-only self-calibration:

   0>selfcal
   Performing phase self-cal
   Adding 49 model components to the UV plane model.
   The established model now contains 49 components and 5.43211 Jy

   Correcting IF 1.
    A total of 2187 telescope corrections were flagged in sub-array 1.

   Fit before self-cal, rms=0.333969Jy  sigma=1.037002
   Fit after  self-cal, rms=0.325501Jy  sigma=1.012208

   Reinstating the default IF.
   0>

2. Amplitude and phase self-calibration with a solution interval.

   0>selfcal true,true,1440
   Performing amp+phase self-cal over 1440 minute time intervals

   Correcting IF 1.
    A total of 222 telescope corrections were flagged in sub-array 1.

   Fit before self-cal, rms=0.325501Jy  sigma=1.012208
   Fit after  self-cal, rms=0.255853Jy  sigma=0.747795

   Reinstating the default IF.
   0>

All but the first line of each example are responses from 'selfcal'.

PARAMETERS
----------
doamp   - (Default=false)
          If this parameter is omitted or given as false, only phase
          corrections are calculated and applied. Alternatively, if
          doamp=true telescope amplitude corrections will also be
          calculated and applied.

dofloat - (Default=false)
```

```
          If doamp=true, then dofloat specifies how the amplitude
          corrections are to be applied. Initially the corrections are
          applied verbatim to the visibilities. If dofloat is true
          then this is all that occurs. However if dofloat is false
          then the total amplitude self-cal corrections so far
          applied to the data, by this and previous invocations of
          selfcal and gscale, are summed over all integrations and
          telescopes to form a mean, and then all corrections are
          divided through by this number to normalize them. This
          provides an established but hard to justify means of
          anchoring the flux scale, in the event that feedback in the
          CLEAN+selfcal loop becomes slightly positive. It is also
          often abused as a means to get amplitude self-cal to work
          before the model has been completed at short UV spacings. If
          you are tempted to do this please look at the help given for
          the selftaper command.

solint  - The solution interval in minutes.
          Solutions are calculated within top-hat solution bins of
          this width and then are smoothed with a gaussian filter.
          The half power point of the filter in the Fourier plane is
          at 1/(2.solint). According to the Shannon sampling theorem
          this is the highest frequency that can be sampled with a
          sample grid spacing of solint.

CONTEXT
-------
Self-calibration is a means to finding self-consistent telescope based
amplitude and phase corrections, through comparison of the observed
data to an approximate model of the source structure. The algorithm
implemented here performs least-squares minimization. It was based on
sample code provided by Tim Cornwell.

As explained in the 'clean' help topic, self-calibration with
'selfcal' is usually combined in a loop with 'clean' and a number of
auxiliary data editing, display etc.. commands.

The initial model to use with selfcal may either be provided by a few
iterations of CLEAN, or by an external model read in with the rmodel
command. Such an external model could come from model fitting, or be
the model from a different map of the same source.

It is strictly recommended that one initially avoid amplitude
self-calibration, and only use phase self-calibration until the model
flux from CLEAN reaches that of the data, as displayed in radplot. Only
at this point should amplitude self-calibration be used to remove
amplitude errors. If you have trouble getting all the flux at short UV
spacings, try switching to natural weighting (see help uvweight)
and/or to using a UV-taper (see help uvtaper) before continuing
CLEANing. This may reveal the extended emission implied by the extra
```

flux at short spacings. If this still doesn't reveal any more
believable flux then, and only then attempt amplitude self-cal, but be
sure to use the selftaper command to weight down the significance of
the badly fitting short UV spacings. If you fail to use selftaper in
this way then selfcal will happily attempt to drag the short UV
spacing visibilities down to fit the erroneously low model.

When interleaved applications of clean and selfcal start to provide
diminishing returns, the residual map (as displayed by 'mapplot map')
should appear to contain only noise and be devoid of beam-shaped
features. Depending on the quality of the data, this may not always be
achievable. If artifacts remain after many cycles of clean and self-cal,
then this may indicate, either low-surface brightness extended
emission that will take some time to clean out, or real problems with
the data. Both cases can be determined by examining the fit between
the model and observed visibilities with the 'vplot' command and the
radplot command. Judicious editing may then be used to remove any bad
data.

In addition, self-calibration will fail to find phase-solutions for
any telescope that appears on less than one un-flagged closure triangle at
a given integration and similarly fail to find gain solutions for
telescopes with no un-flagged closure amplitudes. The selfflag command
may be used to specify how to deal with this. The default is to flag
all corrections that can not be deduced. These correction flags are
propagated to the visibilities that they effect when the corrections
are applied to the data.

To assign extra weight to a given telescope during self-calibration,
or to prevent the complex gain of a given telescope from being
changed see help on the selfant command.

Application of selfcal to multiple sub-arrays, IFs and polarizations
---
Selfcal is applied separately to each sub-array of each IF.
Corrections accumulated in this fashion are propogated to all
spectral-line channels and polarizations in the same IFs and
sub-arrays. Thus by careful mapping and self-calibration of a strong
spectral-line channel you will also be correcting the phases and
amplitudes of the weaker channels so that they can sub-sequently be
cleaned.

Agreement factors

Selfcal displays two agreement factors.

The one denoted 'rms' is the root-mean-square difference between the
model and observed visibilities, measured in Jy. This is formed as the
mean of the squares of the amplitude difference vectors between the
model and observed visibilities.

```
The second, which is denoted by the name 'sigma', is the root mean
square of the squared difference between the data and the model
(taking the real and imaginary parts of visibilities as separate
measurements) divided by the individual variances implied by the
visibility weights. This would be equivalent to the square-root of the
reduced chi-squared, except that no account is taken of the number of
degrees of freedom implied by the number of gains being varied.

RELATED COMMANDS
----------------
selfflag  - Used to control the fate of un-correctable data.
selftaper - Used to down-weight short baselines during selfcal.
selflims  - Used to set limits to amp and phase corrections in selfcal.
selfant   - Set antenna based constraints in selfcal.
gscal     - Calculate overall telescope amplitude corrections.
startmod  - Phase selfcal to a starting model then discard the model.
corplot   - Display and allow editing of corrections.
uncalib   - Remove selected parts of corrections.
```

selfflag

```
Control the identification and fate of un-correctable visibilities.

  selfflag doflag, n_phase, n_amp

EXAMPLES
--------

1. To specify that a minimum of 3 telescopes for phase, and 4 telescopes
   for amplitude selfcal must exist in a closed loop of a given solution
   bin, or the solution bin will be flagged, type:

   0>selfflag true,3,4
   - In phase-only self-cal, good data on baselines that are not in closed
     arrays of at least 3 telescopes will be flagged.
   - In amplitude self-cal, good data on baselines that are not in closed
     arrays of at least 4 telescopes will be flagged.
   0>

2. To specify the same as two, but instead of flagging the bad solution
   bins, just don't correct them, type:

   0>selfflag false,3,4
   - In phase-only self-cal, good data on baselines that are not in closed
     arrays of at least 3 telescopes will not be used.
   - In amplitude self-cal, good data on baselines that are not in closed
     arrays of at least 4 telescopes will not be used.
   0>

3. To specify that all un-flagged data shoud be used in selfcal, type:

   0>selfflag false,0,0
   - In phase-only self-cal, all un-flagged data will be used
   - In amplitude self-cal, all un-flagged data will be used
   0>

All but the first line of each example are responses from 'selfflag'.


PARAMETERS
----------
doflag  - Flag un-correctable visibilities?
          This controls what happens to visibilities that are found
          to be uncorrectable in subsequent invocations of selfcal.
          If this argument is false, the visibilities are left
          un-corrected. If true they are flagged.

n_phase - The minimum number of telescopes required for a phase
          solution. In theory the minimum number of connected
```

telescopes required to form a constrained phase self-cal solution is 3. See below for further discussion.

n_amp - The minimum number of telescopes required for an amplitude solution. In theory the minimum number of connected telescopes required to form a constrained amplitude phase self-cal solution is 4. See below for further discussion.

If no arguments are provided, the current settings are displayed.

Whenever the observe command is used, all the above values are reset, to the values that would be set by typing:

```
selfflag true ,3 , 4
```

CONTEXT

This command determines the behavior of subsequent invocations of the selfcal and gscale self-calibration commands when they encounter un-constrained visibilities.

Self-calibration implicitly relies on the existence of closure phases for phase solutions, and closure amplitudes for amplitude solutions. To form a closure phase requires at least 3 connected telescopes in a closed loop, and to form a closure amplitude requires at least four.

Before attempting to ascertain corrections for a given integration, the current self-calibration algorithms attempt to determine if there are sufficient un-flagged visibilities to constrain solutions for each telescope. They do this in the following manner.

First they identify which telescopes lie on closed baseline paths. Only visibilities from these telescopes can be used in self-calibration. If a prior call to selfflag set dogain to true, then the rest of the un-flagged visibilities are flagged at this point, since they are totally un-correctable by self-calibration and will come to dominate the goodness of fit and prevent the fit from converging.

The number of correctable telescopes is then counted and compared against n_phase if performing phase-only selfcal, or against n_amp if amplitudes are being corrected. If there are insufficient telescopes to attempt a solution and 'doflag' is set to true, then the correction is flagged, and when the corrections are applied to the data, such correction flags are propagated to all affected the visibilities. These flags can be globally removed with the 'uncalib' command, or individually applied or removed with the 'corplot' command.

Since it is impossible to have fewer than 3 telescopes forming a closed array, if the p_mintel (a_mintel for phase selfcal) is set to

```
less than or equal to 2 then the above checks will be turned off, no
flagging will be done and all visibilities will be used in selfcal.

Note that if n_phase and/or n_amp are lowered below their defaults
(3,4) then because there are too few constraints in integrations that
benefit from this, the resulting visibilities will fit too well to the
model. Needless to say, this is not recommended.

RELATED COMMANDS
----------------
selfcal   - Self-calibrate data with the current model.
selftaper - Used to down-weight short baselines during selfcal.
selflims  - Used to set limits to amp and phase corrections in selfcal.
selfant   - Set antenna based constraints in selfcal.
gscale    - Finds overall amplitude corrections for telescopes.
startmod  - Phase selfcal to a starting model then discard the model.
corplot   - Display and allow editing of corrections.
uncalib   - Remove selected parts of corrections.
```

selflims

```
Set limits on acceptable amplitude and phase corrections in selfcal.

  selflims maxamp, maxphs

EXAMPLES
--------

1. To prevent selfcal from making amplitude corrections of more than
   1.1 (unitless scale factor), or phase corrections of more that 10
   degrees, type:

   0>selflims 1.1,10
   Selfcal amplitude corrections will be limited to 0.909091 -> 1.1.
   Selfcal phase corrections will be limited to -10 -> 10 degrees.
   0>

   All but the first line are the response from selflims confirming
   the new limits.

2. To display the currently selected limits omit all arguments:

   0>selflims
   Selfcal amplitude corrections will be limited to 0.909091 -> 1.1.
   Selfcal phase corrections will be limited to -10 -> 10 degrees.
   0>

3. To cancel all limits type:

   0>selflims 0,0
   Selfcal amplitude corrections will not be limited.
   Selfcal phase corrections will not be limited.
   0>

PARAMETERS
----------
maxamp   -   If maxamp < 1 then no limit will be placed on amplitude
             corrections. Otherwise selfcal solution intervals that
             result in one or more amplitude corrections outside
             the range 1/maxamp to maxamp will be left un-corrected.

maxphs   -   If maxphs <= 0 then no limit will be placed on amplitude
             corrections. Otherwise selfcal solution intervals that
             result in one or more phase corrections outside
             the range -maxphs to maxphs degrees will be left
             un-corrected.

When a new data-set is read in using the 'observe' command the
limits are reset to provide no limits on corrections.
```

```
CONTEXT
-------
In some data sets where the data is sparse, noisy or not well
constrained for other reasons, selfcal may produce ridiculously large
aberrant corrections. The selflims command is used before calling
selfcal to set limits on the allowed corrections.

Note that rejection of the solution for a given solution bin does NOT
result in the effected visibilities being flagged - regardless of the
flagging disposition set by any previous use of the selfflag command.

RELATED COMMANDS
----------------
selfcal   - Perform self-calibration.
selfflag  - Used to control the fate of un-correctable data.
selftaper - Used to down-weight short baselines during selfcal.
selfant   - Set antenna based constraints in selfcal.
```

selftaper

```
Sets a (1 - gaussian) taper to weight down SHORT baselines.

  selftaper gaussian_value, gaussian_radius

EXAMPLE
-------

1. To set a gaussian taper.

   0>selftaper 0.1,10
   Selfcal gaussian taper: value 0.1 at UV radius = 10 mega-wavelengths.
   0>

   The second line is the response from the selftaper command, confirming
   the taper selection.

2. To see the currently selected taper value omit all arguments:

   0>selftaper
   Selfcal gaussian taper: value 0.1 at UV radius = 10 mega-wavelengths.
   0>

3. To cancel a previously selected gaussian taper, type:

   0>selftaper 0
   No selfcal UV-taper is currently set.
   0>

PARAMETERS
----------
gaussian_value  - The value of the (1 - gaussian) taper at
                  'gaussian_radius'. Valid values lie between 0 -> 1
                  exclusive. Other values cause the cancellation of
                  any existing gaussian taper.
gaussian_radius - The UV radius at which (1 - gaussian) taper should
                  have RISEN to 'gaussian_value'. (values <= 0
                  de-select gaussian tapering). Unless changed with
                  the mapunits command, the units are
                  million-wavelengths.

To cancel a previous gaussian taper you should type: selftaper 0
Whenever a new UV data set is read with the 'observe' command
any existing gaussian taper is cancelled.

CONTEXT
-------
When required, this command should be called before using the selfcal
command.
```

```
Repeated cycles of clean tend to build up a model that first becomes
complete on long baselines. If amplitude selfcal is applied at this
point it will probably find solutions that pull down the observed
amplitudes at the shorter UV radii to match the incomplete model
there. To circumvent this, you should get selfcal to heavily weight
down the short baselines wrt the longer baselines by calling
selftaper.

A good indication of where the model and observed visibilities
diverge is given by the plot of UV amplitude vs UV radius in radplot.

Selftaper forces subsequent invocations of selfcal to weight down
the visibilities as a function of radius. The form of this function
is.

 (1-gaussian(uv_radius))

In detail:

 (1 - exp(log(1-gaussian_value)*(uv_radius/gaussian_radius)^2)

This goes from 0 at zero UV radius, reaches value=gaussian_value at
a UV radius=gaussian_radius and approaches 1 as UV radius tends
to infinity.

RELATED COMMANDS
----------------
selfcal   - Performs self-calibration.
selflims  - Used to set limits to amp and phase corrections in selfcal.
selfflag  - Used to control the fate of un-correctable data.
selfant   - Set antenna based constraints in selfcal.
gscal     - Calculate overall telescope amplitude corrections.
startmod  - Phase selfcal to a starting model then discard the model.
```

setcont

Add the current model to the continuum model.

```
  setcont
```

EXAMPLE

```
0>setcont
Added 20 components to the continuum model.
0>
```

CONTEXT

In observations of spectral-line sources, background continuum is often present. If the spectral-line features of the source are of primary interest then the constant contribution from the continuum part of the source should be removed before mapping individual spectral-line channels.

The usual way that this is done is to map channels that do not contain any spectral line features. This results in a clean-component model of the continuum. This model is then subtracted from the channels that do have spectral-line emission, leaving only the spectral-line features to be mapped.

While, in theory the subtraction of the continuum model could be done either in the map plane, or in the UV plane, in general it is more accurate to do it in the UV plane, and this is what difmap allows you to do.

Difmap differs from other packages in the way that it does this, in that it employs residual mapping techniques to make continuum subtraction more flexible. In difmap the continuum model is never subtracted directly from the observed visibilities. Instead difmap maintains the continuum model as a part of the established model, (which is subtracted on-the-fly during gridding). When the residual map is restored to display the clean map, the continuum portion of the established model is not added into the map along with the rest of the model, thus leaving just the spectral-line portion of the map.

The advantages of this approach are:

1. The continuum model can be adjusted or deleted at any time without affecting the observed UV data.

2. Since the model visibilities and the observed visibilities are kept apart, it is still possible to use self-calibration after a continuum model has been installed.

3. It may be quicker given that the subtraction is only performed on
   channels that are actually mapped.

The disadvatages are:

1. It is not possible to take continuum-subtracted visibilities into
   another package, since the model is saved as a model file separate
   from the UV FITS file.

Another feature that may be seen as an advatage by some, and a
disadvantage by others, is that radplot and other visibility plotting
commands, display un-subtracted visibilities.

USAGE

The 'setcont' command adds the current tentative and established
models to any existing continuum model.

For example, say one had a source with spectral-line emission only in
channels 21-29 of a 40 channel observation:

1. To determine a continuum model one would use the select command to
   select channels 1..20 and channels 30..40, since these channels
   only contain continuum.

2. Make the best possible map from these channels, using clean or
   modelfit, combined with selfcal if the continuum is strong enough.
   All the selfcal corrections are applied across all channels, so in
   correcting the continuum channels you also correct the
   spectral-line channels.

3. Use the setcont command to add the model made in (2) to the
   continuum model.

4. To check the continuum subtraction, select a single one of the
   continuum only channels, and display the residual map with mapplot.
   If this reveals any structure then the continuum model is not
   correct, and further cleaning etc.. should be applied. Go back to
   step 1, and perhaps try selecting a better set of continuum
   channels. If you do any further cleaning, then use the setcont
   command to update the continuum model with the new components.

5. If the continuum was too weak for self-calibration to be feasible,
   but one or more of the spectral-line features is strong enough,
   select the strong channel, make a map of it and perform self-cal as
   necessary. If significant corrections were made then, go back to
   step 1, to improve on the continuum model.

6. Map each channel containing spectral-line features. Use the

```
    mapl cln

   command to see the clean map, uncontaminated by the continuum.

OTHER COMMANDS THAT AFFECT THE CONTINUUM MODEL
----------------------------------------------

wmodel:

 With the addition of the continuum model, difmap now has three models
 that can be addressed by the user. For instance the clrmod command
 allows you to specifically select which of these get cleared.

 After using the select command, you are advised to type:

  0>clrmod true

 This clears both the established and tentative models that were built
 up during the previous channel selection, but preserves the continuum
 model for the new channel selection.

 If you want to clear the continuum model, the optional 3rd argument
 of clrmod must be given as 'true'.

wmodel and rmodel:

 The wmodel and rmodel commands default to writing/reading the
 non-continuum parts of the established and tentative models. The
 optional second agument is required to ask it to separately handle the
 continuum part. See help wmodel and help rmodel, for details.

save and get:

 The 'save' command saves continuum models separately from the normal
 models, in a file with suffix ".cmod". The 'get' command looks for a
 file with this extension and if found, reads the file, placing the
 model directly in the continuum model.
```

shift

```
Shift the observation phase-center, CLEAN window and model positions.

  shift xshift, yshift

EXAMPLES
--------

1. 0>shift 10,-1
   shift: Shifting UV data, clean models and windows by: 10 (mas) East
   shift: Shifting UV data, clean models and windows by: -1 (mas) North
   Total accumulated eastward shift  = 10 (mas).
   Total accumulated northward shift = -1 (mas).
   0>

   All but the first line are responses from the 'shift' command.

2. Shifts are applied incrementally. To see what the accumulated
   shifts are, omit all arguments:

   0>shift
   Total accumulated eastward shift  = 10 (mas).
   Total accumulated northward shift = -1 (mas).
   0>

3. To remove the accumulated shift use the 'unshift' command.

   0>unshift
   unshift: Removing accumulated position shifts.
   0>

PARAMETERS
----------
xshift - The distance to shift the source Eastwards.
yshift - The distance to shift the source Northwards.

CONTEXT
-------
This command may be called at any time. It is useful for checking
whether there is flux beyond the bounds of the map. It is also useful
if one has a single sided source with a bright core at the center of
the map. In the latter case, half of the map area is wasted. In this
case the shift command may be used to better utilize the space
available and thus allow a smaller map grid. A more complex use is to
map a large area containing several widely separated sources. In this
case the shift command is used to center the map on one source at a
time while it is cleaned. This has the advantage that a smaller map
grid may then be utilised to realize faster mapping and less memory
usage.
```

The 'shift' command modifies the observed and model visibilities
simply by moving the phase center of the map. It also modifies the
latest and established model component lists and any clean windows
to have positions wrt the new phase center.

SIDE EFFECTS

The modifications to the UV data invalidate the current residual map.
This will be re-calculated on the next 'invert'. Thus shifting the
data incurs the overhead of an extra 'invert'.

ASSOCIATED COMMANDS
---
unshift - Undo accumulated position shifts from the data, windows and models.

showhist

Display the history that was recorded with the current observation.

```
showhist
```

This command displays a chronological list of entries made in the
history file that was loaded with the current observation.

See 'help help' for directions on using the difmap pager.

showpar

```
Display a list of difmap configuration parameters.

  showpar

EXAMPLE
-------

0>showpar
Difmap configuration state:
mapunits mas
select I, 1, 1
uvtaper 0, 0
uvrange 0, 0
uvweight 2, 0, false
uvzero 0
selftaper 0, 0
selflims 0, 0
xyrange 0, 0, 0, 0
integer niter; niter=100
float gain; gain=0.05
float cutoff; cutoff=0
float cmul; cmul=0
logical docont; docont=true
mapcolor grey, 1.000000, 0.500000
mapfunc linear, 0.000000, 0.000000
string vflags; vflags=""
string rflags; rflags=""
string pflags; pflags=""
selfflag true, 3, 4
float levs(1)
levs(1:1) = 0
0>

CONTEXT
-------
Some aspects of Difmap behavior are controlled by parameters set
through configuration variables and commands. The 'showpar' command
lists the current state of these parameters. It does this in an
indirect manner, by showing the command file that the 'save' command
would record if invoked to record difmap's internal state.

This is not the most convenient way that one could conceive of, but
unless I get a chance to re-write the difmap interface, I have
little choice but to show the parameters in this fashion.
```

specbase

Select baselines to be displayed by specplot.

```
  specbase mode, baseline_group1, baseline_group2, ...
```

EXAMPLE
----

1. To see what baselines are currently selected, omit all arguments.

```
   0>specbase
   Specplot will plot baselines of *
   0>
```

2. To request that all baselines be plotted separately.

```
   0>specbase split,*
   Specplot will plot baselines of *
   0>
```

3. To request that all baselines be combined to construct a single
   spectrum:

```
   0>specbase group,*
   Specplot will plot baseline groups:
    *
   0>
```

3. Specify multiple groups of baselines to plot, each consisting of
   all baselines of a different telescope from sub-array 2.

```
   0>specbase group, 2:br, 2:fd, 2:hn, 2:kp
   Specplot baseline selections:
    2:BR
    2:FD
    2:HN
    2:KP
   0>
```

4. To request two spectra, one from all baselines of the BONN telescope
   except those of the OVRO telescope, and a second comprised from all
   baselines of the OVRO telescope except those of the BONN telescope:

```
   0>specbase group, bonn ! ovro, ovro !bonn
   Specplot will plot baseline groups:
    1:BONN ! 1:OVRO
    1:OVRO ! 1:BONN
   0>
```

```
5. To display one spectrum for each baseline of antenna AN2 from
   sub-array 2:

   0>specbase split, 2:an2
   Specplot will plot baselines of 2:AN2
   0>

ARGUMENTS
---------
mode                -   This tells specplot how to interpret the
                        baseline group arguments. It takes two values:

                         split  -  Split the first group into its
                                   component baselines and plot one
                                   spectrum per baseline.

                         group  -  Plot one spectrum per group of
                                   baselines.

baseline-group,...  -   One or more groups of baseline specifications.
                        Type 'help antenna_names' for legal baseline
                        specifications, and see below to determine how
                        to combine them.

To see the current selection, type the specbase command with no
arguments.

CONTEXT
-------
The specplot command plots scalar and vector averaged visibility
spectra. Visibilities are selected by polarization, time range, UV
radius range, and baseline selections. The specbase command is
responsible for supplying baseline selections, either as groups of
baselines or as single baselines taken from a single group.

Where more than one baseline selection is given, spectra can be
plotted for each of them separately. The 'specorder' command can be
used to direct when to change from one baseline selection to the
next while plotting spectra.

BASELINE GROUPS
--------------
Each argument of the 'specbase' command is a group of baseline
specifications, each specification describing one or more baselines to
be included or excluded. Each specification is preceded by either '+'
or '!'. Those preceded by '+' add to the group of baselines to be
averaged, whereas those preceded by '!' subtract from the group of
baselines established by earlier specifications. For example a group
consisting of:
```

```
 "ovro + bonn ! ovro-bonn"

means include all baselines of OVRO and all baselines of BONN except
baseline OVRO-BONN. Note that the order in which specifications are
listed is important. If the above were re-ordered to:

 "ovro ! ovro-bonn + bonn"

The !ovro-bonn component would have no effect because the +bonn
component would re-introduce the baseline that was just removed.

The first specification is implicitly preceded by '+' to make it
additive, however if the first specification is explicitly preceded by
'!' then this is interpretted as being equivalent to "* !". For
example:

 "!2"

means included all baselines of all sub-arrays except those of
sub-array 2.

Other examples are given in the EXAMPLE section at the beginning of
this help file.

RELATED COMMANDS
----------------
specplot   -  Plot time-averaged visibility spectra.
specopt    -  Preset specplot display options.
specsmooth -  Preset the spectral resolution displayed by specplot.
specorder  -  Set the order in which spectra are to be displayed.
specpol    -  Select the list of polarizations to be displayed by specplot.
spectime   -  Select the time ranges to be displayed by specplot.
specuvr    -  Select the UV radius ranges to be displayed by specplot.
```

specopt

```
Preset specplot display options.

  specopt x_units, flags

EXAMPLES
--------

1. To see the currently selected options without changing them, omit
   all arguments.

   0>specopt
   Specplot x-axis=channels  flags="3jJe".
   0>

2. To select an X-axis that is labelled in units of frequency instead
   of channels, and change the flags such that lines are drawn as
   simple vectors instead of bins.

   0>specopt 5, frequency, 3j
   Specplot nplot=5  x-axis=frequency  flags="3j".
   0>

ARGUMENTS
---------
x_units   -   Remembered. Initial default = channel
              The units plotted on the X-axis of each spectrum.
              Valid values are:
                channels  -  Spectral-line channels.
                frequency -  Spectral-line channel center frequencies.
              Unambiguous abbreviations are recognized.

flags     -   Remembered. Initial default = "3jJ".
              Plot option flags.
              Many of the toggled options that are bound to keyboard
              keys for interactive use in specplot, can be preset by
              placing those same keys in a string.
              The initial default string of flags specifies that
              both amplitude and phase will be plotted (3), that
              neighboring points will be joined (j) to form a
              histogram style plot (J) and that error bars be plotted
              (e). See 'help specplot' for the meaning of other toggle
              options.

CONTEXT
-------
The specplot command plots time-averaged visibility spectra. By
default it plots one spectrum for each baseline in one's observation,
at 3 plots per page, plotting each as amplitude and phase versus
```

channel number. Neighboring points are joined by lines, using a style similar to a histogram to indicate how the data are binned into channels.

The x-axis of the plotted spectra is always plotted in order of increasing channel number, and IF number. However the values plotted along the axis can be changed to other forms with the 'x_unit' argument. This effects the X-axis scale, but not the ordering of points. Thus two IFs plotted side by side may show frequencies that increase in opposite directions.

There are a number of other binary options that effect the way that spectra are plotted but do not require that the spectra be reconstructed. Interactively these are toggled via keyboard keys and those options will be remembered between specplot sessions. These can be seen by typing specopt without any arguments, or they can be replaced by specifying a new string of option flags with the 'flags' argument. The individual flags are described in the specplot help pages.

Related commands
---
specplot - Plot time-averaged visibility spectra.
specsmooth - Preset the spectral resolution displayed by specplot.
specorder - Set the order in which spectra are to be displayed.
specbase - Select the baselines to be displayed by specplot.
specpol - Select the list of polarizations to be displayed by specplot.
spectime - Select the time ranges to be displayed by specplot.
specuvr - Select the UV radius ranges to be displayed by specplot.

specorder

```
Set the order in which specplot plots spectra.

  specorder selection-type1, ...

EXAMPLES
--------

1. To see the currently selected plot order without changing it, omit
   all arguments.

   0>specorder
   Specplot selection order: baseline
   0>

2. To plot one spectrum for each scan that is distinguishable from its
   neighbor by a 1 hour time gap:

   0>spectime 306/07:56:44, 398/08:16:19, -60
   Specplot time range 306/07:56:44 - 398/08:10:52,  scan separation=60 mins
   0>specorder time
   Specplot selection order: time
   0>specplot

3. To change from plotting one spectrum per baseline selection, to
   plotting 1 page per baseline, partitioned into one spectrum of
   each of 4 stokes parameters.

   0>specpol I,Q,U,V
   Specplot polarization selections: I, Q, U, V
   0>specopt 4
   Specplot nplot=4  x-axis=channels  flags="3jJ".
   0>specorder polarization, baseline
   Specplot selection order: polarization baseline
   0>specplot

4. To see how the spectrum averaged over all baselines, changes with
   UV radius range.

   0>specuvr 0,0,10
   Specplot UV range: uvmin=0  uvmax=151.407  uvstep=10 (kilo-wavelengths)
   0>specbase group,*
   Specplot will plot baseline groups:
    *
   0>specorder uvrange
   Specplot selection order: uvrange
   0>specplot
```

```
ARGUMENTS
---------

selection-type_1   -  The type of the selection that will be
                      incremented the fastest. The recognized
                      selection types are:
                       baseline     -  Baseline selections established
                                       with the 'specbase' command.
                       polarization -  Polarization selections
                                       established with the 'specpol'
                                       command.
                       time         -  Time-range selections
                                       established with the 'spectime'
                                       command.
                       uvrange      -  UV-radius range selections
                                       established with the 'specuvr'
                                       command.
...

selection-type_n   -  The type of the selection that will be
                      incremented each time that selection types
                      1 -> n-1 have been exhausted.

CONTEXT
-------
The specplot command plots scalar and vector averaged visibility
spectra. The visibilities that are averaged to form each spectrum are
selected by U-V radius range, polarization, time and baseline.

On a given page only one of these quantities is allowed to change
between plotted spectra, but when all values of that quantity have
been exhausted, one of the other quantities may be incremented before
starting the next page. The order in which the different quantities
are incremented is determined by the 'specorder' command.

By default, only the baseline selection specified by the 'specbase'
command is allowed to increment. This behavior is the equivalent of
what one would see after typing:

 0>specorder baseline

Alternatively, if one wanted to look at the spectrum of a specific
group of baselines at different times, one would call the specbase and
spectime commands to select the desired baseline group and the time
ranges and then type:

 0>specorder time

If one wanted to extend this such that when one group of baselines had
been displayed to each of the desired time ranges, a second group of
```

baselines was plotted over the same time ranges, one would call the
specbase command to select two baseline groups and type:

```
 0>specorder time, baseline
```

RELATED COMMANDS

```
specopt    -  Preset specplot display options.
specsmooth -  Preset the spectral resolution displayed by specplot.
specbase   -  Select the baselines to be displayed by specplot.
specpol    -  Select the list of polarizations to be displayed by specplot.
spectime   -  Select the time ranges to be displayed by specplot.
specuvr    -  Select the UV radius ranges to be displayed by specplot.
```

specplot

```
Plot time-averaged visibility spectra.

  specplot nplot, aver_mode, ca, cb, amin, amax, pmin, pmax, npage

EXAMPLES
--------

1. Plot vector averaged spectra, autoscaled in amplitude, phase
   and channels, using the current defaults for what gets plotted.

   0>specplot
   For help move the cursor into the plot window and press 'H'.
   0>

2. As in example 1, but use scalar averaging to construct
   spectra instead of vector averages, and restrict the X-axis range
   to channels 10 to 20.

   0>specplot 0, scalar, 10, 20
   For help move the cursor into the plot window and press 'H'.
   0>

2. Change all the default parameters that determine what goes into
   each spectrum and how to plot them, then plot the result.

   0>specbase split, kp
   Specplot will plot baselines of 1:KP

   0>specpol I,Q,U,V
   Specplot polarization selections: I, Q, U, V

   0>spectime 355/14:43:29, 356/05, -20
   Specplot time range 355/14:43:29 - 356/04:20:30,  scan separation=20 mins

   0>specsmooth channels, hanning, 3
   Specplot smoothing:  units=channels  window=hanning  fwhm=3

   0>specopt frequency, "3j+"
   Specplot x-axis=frequency  flags="3+j".

   0>specorder polarization, baseline
   Specplot selection order: polarization baseline

   0>specplot 4, vector, 10, 20, 0, 1.3, -180, 180
   For help move the cursor into the plot window and press 'H'.
   0>

ARGUMENTS
```

```
---------
nplot     -   Default = 0 (this actually selects 3 plots per page).
              The number of spectra to plot on each page.
              Note that 'nplot' spectra are simultaneously constructed
              in a single pass through the data, so it is faster to
              plot a few multi-plot pages than to plot a lot of pages
              of single plots.

aver_mode -   Default = vector
              How to time-average visibilities. Valid modes are:
               vector       -  Vector average visibilities.
               scalar       -  Scalar average visibilities.

ca,cb     -   Default = (All channels observed).
              The numbers of the first and last channels to be
              plotted, or 0,0 to select all channels. Channels are
              numbered contiguously from the first channel of the
              first observed IF to the last channel of the last
              observed IF.

amin,amax -   Default = (Autoscale).
              The plotted range of amplitudes, or 0,0 to select
              individually autoscaled amplitude sub-plots.

pmin,pmax -   Default = -180,180.
              The plotted range of phases (degrees).

npage     -   Default = 0
              When plotting to a non-interactive device and npage is
              greater than 0, then a maxmimum of npage pages will be
              plotted.

CONTEXT
-------
The specplot command plots time-averaged visibility spectra as
amplitude and phase versus either spectral-line channel or frequency.
The individual spectra of multiple IFs are plotted side by side on the
page. Each page is also divided vertically to display multiple
spectra, each differing from the last in either the polarization, time
range, UV radius range, or the set of baselines averaged.

Note that the current stream selection is irrelevant to 'specplot',
and the 'select' command need not have been called before invoking
'specplot'. This allows one to decide what channels and polarization
to select in advance by looking at visibility spectra with 'specplot'.

The averaging mode, 'aver_mode'
-------------------------------
Spectra are formed from a weighted average of selected visibilities.
Specplot supports two averaging modes:
```

1. Vector averaging.

   When visibilities are vector averaged the real and imaginary parts
   of each visibility are individually averaged and later converted to
   amplitude and phase for plotting.

2. Scalar averaging.

   When visibilities are scalar averaged the real and imaginary parts
   of each visibility are first converted to amplitude and phase. The
   amplitudes and phases are then individually averaged.
   The resulting amplitude spectrum is biased updwards by noise but is
   independant of phase calibration and position shifts.

Selecting the number of plots per page.

To form a spectrum the 'specplot' command has to read raw visibilities
from disk and apply accumulated edits, self-calibration corrections,
resoff corrections, and position shifts. For large data-sets this is
time consuming, so rather than repeat this separately for each
spectrum, the 'specplot' command constructs a whole page full of
spectra from a single pass through the data. This takes more memory
but is potentially much faster when more than one plot is requested
per page. The number of plots per page can be specified on the command
line and/or interactively.

The order in which spectra are plotted.

The visibilities that are averaged to form each spectrum are selected
by U-V radius range, polarization, time and baseline.

On a given page only one of these quantities is allowed to change
between plotted spectra, but when all values of that quantity have
been exhausted, one of the other quantities may be incremented before
starting the next page. The order in which the different quantities
are incremented is determined by the 'specorder' command. By default,
only the baseline selection specified by the 'specbase' command is
allowed to increment. This behavior is the equivalent of what one
would see after typing:

 0>specorder baseline

If one wanted the polarization selection to be incremented each time
that spectra for all baselines had been plotted, one would type:

 0>specorder baseline, polarization

The increment order can also be changed incteratively with the 'o'
key (see below).

```
See 'help specorder' for the names of each of the selection types.

X-axis options
--------------
The type of X-axis that is plotted can be changed with the 'specopt'
command. By default, amplitude and phase are plotted versus channel
number.

Spectral resolution
-------------------
The resolution of the plotted spectra can be reduced by smoothing
them. The specsmooth command specifies the smoothing parameters to be
used. The smoothing width may be specified in terms of channels or
frequency.

Error bars
----------
By default error bars are plotted for each spectral-line channel. They
are toggled on or off with the 'e' key. They are formed from the
individual visibility weights that go into the weighted average for
each channel, which are interpretted as being the reciprocal of the
square of the amplitude uncertainty. If this is not true, see the
'wtscale' command. The error bars also take into account any smoothing
that has been applied during plotting. This is described in the help
pages of the specsmooth command.

Plot styles
-----------
By default, neighboring channels are plotted joined by lines in a
staircase or histogram-like manner. This shows the real channel widths
and sampling. Altenatively, lines can be drawn between the centers of
neigboring channels. The latter looks aesthetically better when
multi-channel smoothing has been selected. A third alternative is to
simply plot each spectral-line channel as an isolated point. Points
are then plotted at the center of each channel.

Interactive options
-------------------
At any time while running specplot, a list of the key bindings that
specplot understands will be displayed if you hit the 'H' key on your
keyboard. The current key bindings include:

 H - List all key bindings.

 X - Exit specplot (right-mouse-button).

 L - Redisplay the current plot.

 N - Display the next page of spectra.
```

```
P - Display the preceding page of spectra.

s - Change the number of spectra plotted per page.
    Beware, this requires a new pass through the data and may take
    some time with a large data-set.

S - Change the plotted spectral resolution by setting or de-selecting
    smoothing parameters.

1 - Plot only amplitudes.

2 - Plot only phases.

3 - Plot both amplitudes and phases.

E - Toggle whether error bars are plotted.

V - Toggle between vector and scalar averaged spectra.
    Beware, this requires a new pass through the data and may take
    some time with a large data-set.

t - Change the baselines, polarization or times used to construct
    spectra.
    You will be asked to specify a selection type name and zero or
    more specification arguments. The specification arguments have
    the same format as the equivalent command-line commands:

     baseline, group|split, baseline_group1, ... (see help specbase).
     polarization, polarization_name1, ...       (see help specpol).
     time, start_time, end_time, scan_time       (see help spectime).
     uvrange, uvmin, uvmax, uvstep               (see help specuvr).

o - Change the order in which selections are incremented.
    You will be asked for one or more selection names, in the same
    format as documented for the 'specorder' command.
    See 'help specorder' for details.

u - Delimit a X-axis range with the cursor (hit u twice for full range).
    Either press this key (u) a second time to undo a previous range
    selection, or delimit the desired X-axis range by pressing the
    'A' key (left mouse button), once at each end of its extent.
    The range selection can be cancelled while in this mode by
    pressing the 'D' key (middle mouse button).

U - Change the X-axis type.
    You will be prompted for the name of a recognized axis type.
    See help specopt for a list of valid type names.

Z - Select a new amplitude or phase range (hit Z twice for full range).
```

```
    Either press this key (Z) a second time to undo a previous range
    selection, or delimit the desired amplitude or phase range by
    pressing the 'A' key (left mouse button), once at each end of its
    extent.
    The range selection can be cancelled while in this mode by
    pressing the 'D' key (middle mouse button).

 j - Toggle whether to join points with lines.
    This toggles whether channel values are plotted as isolated
    points, or are whether they are joined by lines. If joined points
    are selected, there format can be further selected with the 'J'
    key described below.

 J - Toggle between two possible line styles.
    By default the lines are drawn as bins, in a staircase like
    pattern. The alternative is to simply draw straight lines
    directly between the centers of each channel.

 + - Toggle whether to use a crosshair cursor if available.
    If the plot device supports a cross-hair cursor this will be
    substituted for the normal cursor if toggled on with the '+' key.

Related commands
----------------
specopt    -  Preset specplot display options.
specsmooth -  Preset the spectral resolution displayed by specplot.
specorder  -  Set the order in which spectra are to be displayed.
specbase   -  Select the baselines to be displayed by specplot.
specpol    -  Select the list of polarizations to be displayed by specplot.
spectime   -  Select the time ranges to be displayed by specplot.
specuvr    -  Select the UV radius ranges to be displayed by specplot.
```

specpol

Select the list of polarizations to be displayed by specplot.

```
  specpol polarization1, polarization2, ...
```

EXAMPLE
----

1. Select a single polarization.

```
   0>specpol I
   Specplot polarization selections: I
   0>
```

2. Select a list of polarizations.

```
   0>specpol I,Q,U,V
   Specplot polarization selections: I, Q, U, V
   0>
```

3. To see what polarizations are currently selected, omit all arguments.

```
   0>specpol
   Specplot polarization selections: I, Q, U, V
   0>
```

ARGUMENTS
----

polarization1, ... - A list of one or more names of polarizations. Type 'help polarization' for the list of recognized names.

To see the current list omit all arguments.

CONTEXT

The specplot command plots scalar and vector averaged visibility spectra. Visibilities are selected by polarization, time range, UV radius range, and baseline groups. The specpol command is responsible for supplying a list of polarizations.

Where more than one polarization is given, spectra can be plotted for each of them separately. The 'specorder' command can be used to direct when to change from one polarization to the next while plotting spectra.

Recognized polarization names are listed in the on-line help for polarization. To see the list, type:

```
 help polarization

RELATED COMMANDS
----------------
specplot   -  Plot time-averaged visibility spectra.
specopt    -  Preset specplot display options.
specsmooth -  Preset the spectral resolution displayed by specplot.
specorder  -  Set the order in which spectra are to be displayed.
specbase   -  Select baselines to be displayed by specplot.
spectime   -  Select time ranges to be displayed by specplot.
specuvr    -  Select the UV radius ranges to be displayed by specplot.
```

specsmooth

```
Preset the spectral resolution displayed by specplot.

  specsmooth units, window, fwhm

EXAMPLES
--------

1. To examine the current settings, invoke the specsmooth command with
   no arguments:

   0>specsmooth
   Specplot smoothing:  units=channels  window=none  fwhm=0
   0>

2. To have specplot plot smooth spectra versus frequency (GHz) using
   a Hanning window of width 10 KHz (1e-5 GHz):

   0>specsmooth frequency, hanning, 1e-5
   Specplot smoothing:  units=channels  window=hanning  fwhm=1e-05
   0>

ARGUMENTS
---------
units       -   Default=channels
                The units of the smoothing width, chosen from:
                  channels  -  Spectral-line channels.
                  frequency -  Spectral-line channel frequencies.
                Unambiguous abbreviations are recognized.

window      -   Default=none
                The window function used to smooth spectra to a given
                spectral resolution, from:
                  none      -  No smoothing.
                  hanning   -  Hanning smoothing window.
                  gaussian  -  Gaussian smoothing window.
                  boxcar    -  Boxcar smoothing window.
                  sinc      -  Sinc smoothing window
                Unambiguous abbreviations are recognized.
                Details of the smoothing functions are described
                below.

fwhm         -  Default=0.0 (no smoothing)
                The full width at half maximum of the smoothing
                function, in terms of the 'units' argument described
                above.

CONTEXT
-------
```

The specplot command plots time-averaged visibility spectra. By default it plots amplitude and phase versus channel number. The specsmooth command allows one to smooth spectra to reduce the apparent spectral resolution. This potentially reduces noise, so the optionally plotted error bars are modified to reflect this.

While it is often most convenient to specify the width of one's smoothing in terms of spectral-line channels, different IFs can have different frequency increments per channel, so specsmooth allows one to specify the units in which to interpret the width. This choice is independent of the choice of the displayed X-axis units. The latter can be changed with the 'specopt' command.

As with the other specplot setup commands, 'specsmooth' arguments can be changed interactively while plotting, via the capitalized 'S' key. This option prompts for the same arguments as taken by 'specsmooth'.

Smoothing is performed on-the-fly every time that as each spectrum is displayed. The unsmoothed spectra are retained unchanged, so that future changes to the smoothing are independent of previous smoothing choices.

Smoothing functions

Smoothing is accomplished by convolving the data with the chosen smoothing function. Smoothing is performed on the real and imaginary parts of vector averaged spectra, and to the amplitudes and phases of scalar averaged spectra.

In order to describe the details of each smoothing function, let the value plotted along the X-axis be denoted by x, and let:

```
  v = x / (0.5*fwhm).
```

With this tranformation each smoothing function, s(v) has

```
  s(1) = 0.5 * s(0)
```

The area-normalized smoothing functions are then given by

```
  none     s(v) = 1.0 (No smoothing, so fwhm is ignored)

                    sin(pi.v)
  hanning  s(v) = --------------
                  2.pi.v.(1-v^2)

  gaussian s(v) = sqrt[ln(2)/pi] * exp[-ln(2)*v^2]

  boxcar   s(v) = 0.5 for |v| <= 1, and 0 elsewhere
```

```
                 c    sin(c*v)
  sinc     s(v) = -- * --------, with c=1.8954942670340
                 pi    (c*v)
```

If one denotes convolution by the operator (*), the smoothing function by s, the data by f, and the data weights by, w, then the final smoothed spectrum and associated weights are given by:

$$\langle f \rangle = \frac{f.w \ (*) \ s}{w \ (*) \ s}$$

$$\langle w \rangle = \frac{[w \ (*) \ s]^2}{w \ (*) \ s^2}$$

Note that data weights are interpretted as being related to error bars (e) by:

$$w = 1/e^2$$

Related commands

specplot	-	Plot time-averaged visibility spectra.
specopt	-	Preset specplot display options.
specsmooth	-	Preset the spectral resolution displayed by specplot.
specbase	-	Select the baselines to be displayed by specplot.
specpol	-	Select the list of polarizations to be displayed by specplot.
spectime	-	Select the time ranges to be displayed by specplot.
specuvr	-	Select the UV radius ranges to be displayed by specplot.

spectime

Select the range(s) of times to be averaged by the specplot command.

```
  spectime start_time, end_time, scan_time
```

EXAMPLES
----

1. To see the current time ranges omit all arguments.

```
   0>spectime
   Specplot time range 306/07:56:44 - 398/08:16:19,  scan length=132500 mins
   0>
```

2. Select a single time range between 7am and 9am on day 306 of the
   year of observation.

```
   0>spectime 306/07, 306/09
   Specplot time range 306/07:56:44 - 306/08:59:46,  scan length=63.0333 mins
   0>
```

   Note that the time range actually selected is determined by what
   times are actually sampled between the requested times.

3. Split a single time range into a number of 10 minute scans.

```
   0>spectime 306/07, 306/09, 10
   Specplot time range 306/07:56:44 - 306/08:59:46,  scan length=10 mins
   0>
```

3. Split a single time range into its component integrations.

```
   0>spectime 306/07, 306/09, 0
   Specplot time range 306/07:56:44 - 306/08:59:46,  scan length=0 mins
   0>
```

4. Split the time range at time gaps of at least 1 hour (60 minutes).

```
   0>spectime 306/07, 306/09, -60
   Specplot time range 306/07:56:44 - 306/08:59:46,  scan separation=60 mins
   0>
```

ARGUMENTS
----

stime - Default = The time of the first observed integration.
The start time of the overall time range as a string of
form: DDD/HH:MM:SS.sss, where all but the initial DDD can
be omitted (they each default to zero).

```
etime     -  Default = The time of the last observed integration.
             The end time of the overall time range, in the same form
             as 'stime'.

scan_time -  Default = etime - stime
             A scan length or interval (minutes).
             If scan_time >= 0 then the time range stime -> etime will be
             split into sampled periods of up to 'scan_time' minutes.
             If scan_time < 0 then the time range stime -> etime will be
             split wherever there is at least '|scan_time|' minutes
             separating neighbouring integrations.

CONTEXT
-------
The specplot command plots scalar and vector averaged visibility
spectra. Visibilities are selected by polarization, time range, UV
radius range, and baseline groups. The spectime command is responsible
for supplying time ranges.

Where more than one time range is given, spectra can be plotted for
each of them separately. The 'specorder' command can be used to direct
when to change from one time range to the next while plotting spectra.

The arguments of the 'spectime' specify both the overall duration over
which to plot spectra and how to apportioned this duration between
spectra. The spectime command supports two ways to apportion times.

1. To separate the specified duration into multiple scans, each of a
   given length, specify that length, using the 'scan_time' argument,
   as a positive number of minutes.
   Each scan starts with the first sampled integration that follows
   the end of the preceding scan. Individual scans will be shorter than
   the given length where insufficient integrations are available.
   Note that if the specified length is zero, then each scan will
   encompass a single integration.

2. To separate the specified duration into scans that are separated by
   at least a given interval of time, specify the interval, using the
   'scan_time' argument, as a negative number of minutes.

RELATED COMMANDS
----------------
specplot   -  Plot time-averaged visibility spectra.
specopt    -  Preset specplot display options.
specsmooth -  Preset the spectral resolution displayed by specplot.
specorder  -  Set the order in which spectra are to be displayed.
specpol    -  Select the list of polarizations to be displayed by specplot.
specbase   -  Select baselines to be displayed by specplot.
specuvr    -  Select the UV radius ranges to be displayed by specplot.
```

specuvr

```
Select the UV radius ranges to be displayed by specplot.

  specuvr uvmin, uvmax, uvstep

EXAMPLES
--------

1. To see what UV ranges are currently selected, omit all arguments.

   0>specuvr
   Specplot UV range: uvmin=0  uvmax=151.407  uvstep=10 (kilo-wavelengths)
   0>

2. To restrict the UV range to 10 -> 30 kilo-wavelengths.

   0>specuvr 10,30
   Specplot UV range: uvmin=10  uvmax=30  uvstep=20 (kilo-wavelengths)
   0>

3. To see how the spectrum averaged over all baselines, changes with
   UV radius range.

   0>specuvr 0, 0, 10
   Specplot UV range: uvmin=0  uvmax=151.407  uvstep=10 (kilo-wavelengths)
   0>specorder uvrange
   Specplot selection order: uvrange
   0>specbase group, *
   Specplot will plot baseline groups:
    *
   0>specplot

ARGUMENTS
---------
uvmin         - Initial default=0.0
                The minimum UV radius to take visibilities from, measured
                in the wavelength units last established with the mapunits
                command. By default this is mega-wavelengths.

uvmax         - Default=Max UV radius in data.
                The maximum UV radius to take visibilities from, or 0.0
                to select the maximum UV radius available in the data.

uvstep        - Default = (uvmax - uvmin)
                The UV radius increment between spectra, measured in
                the same units as uvmin and uvmax.

To see what the current values of these arguments are, invoke the
specuvr command without any arguments.
```

CONTEXT

The specplot command plots scalar and vector averaged visibility spectra. Visibilities are selected by polarization, time range, UV radius range, and baseline selections. The specuvr command is responsible for supplying UV radius ranges.

Where more than one UV radius range is given (ie uvstep < uvmax-uvmin), spectra can be plotted for each range separately. The 'specorder' command can be used to direct when to change from one UV radius range to the next while plotting spectra.

RELATED COMMANDS
----
specplot - Plot time-averaged visibility spectra.
specopt - Preset specplot display options.
specsmooth - Preset the spectral resolution displayed by specplot.
specorder - Set the order in which spectra are to be displayed.
specbase - Select baselines to be displayed by specplot.
specpol - Select the list of polarizations to be displayed by specplot.
spectime - Select time ranges to be displayed by specplot.

startmod

```
Read a starting model from disk and phase self-calibrate against it.

  startmod starting_model_file_name, solint

EXAMPLE
-------

0>startmod
Applying default point source starting model
Performing phase self-cal
Adding 1 model components to the UV plane model.
The established model now contains 1 components and 1 Jy

Correcting IF 1.
 A total of 21 un-correctable visibilities were flagged in sub-array 1.

Fit before self-cal, rms=3.283113Jy  sigma=10.445014
Fit after  self-cal, rms=3.282763Jy  sigma=10.437578

Reinstating the default IF.
clrmod: All model representations cleared.
Redundant starting model cleared
0>

All but the first line are responses from the startmod command and
its clients.

PARAMETERS
----------

model_file - Default = ""
             The file name containing delta and/or gaussian
             model components. If no file name is given, a point source
             model will be substituted.
             This model will be the starting model used to correct the
             phases via self-cal before mapping begins.
             The model will be discarded after use.

solint     - Default = 0.0.
             The solution interval (minutes). See 'help selfcal' for
             details.

CONTEXT
-------
Invoking startmod is equivalent to the following sequence of commands:

clrmod true
rmodel "somefile.mod"
```

```
selfcal
clrmod true
```

This results in the UV data being phase self-cal'd against a starting model (say from modelfit), without producing residuals between the model and the observed data. Since the model does not become part of the established model, the starting model need only be a coarse estimate of the true flux distribution.

SIDE EFFECTS

Any existing models will be cleared before reading in the starting model and the UV data will be re-inverted by the next operation that requires the residual map.

telname

```
Returns the name of telescope 'itel' of sub-array 'isub'.

  telname itel, isub

EXAMPLE
-------
example 1  -  Print out all (ntel) telescope names in sub-array 1.

0>do i=1,ntel
1>  print telname(i)
1>end do
1:BONN
1:WSRT
1:JBNK1
1:BOLOGNA
1:VLBA_KP
1:VLBA_PT
1:VLBA_LA
1:VLA27
1:OVRO
0>

example 2  -  Display the self-cal corrections for each telescope in turn
              from sub-array 2.

0>
0>do i=1,ntel
1>  corplot `telname(i,2)`
1>end do

Example 3  -  Print the name of the third telescope in sub-array 2.

0>print telname(3,2)
2:OVRO

The "number:" prefix indicates the number of the sub-array to which the
telescope belongs.

PARAMETER
---------
itel  -  The sequential number of the telescope who's name is required.

isub  -  Default: 1
         The number of the sub-array from which the telescope name
         is required.

RELATED FUNCTIONS
-----------------
```

```
ntel - Return the number of telescopes in a given sub-array.
nsub - Return the number of sub-arrays in an observation.
```

tplot

```
Plot time sampling for each telescope of an observation.

  tplot subarray, IF_index

EXAMPLES
--------

1. Displaying telescope sampling on an interactive device.

   0>tplot
   Graphics device/type (? to see list, default /NULL): /xw
   Move the cursor into the plot window and press 'H' for help

   All but the first line of the above is output from tplot.

2. Displaying telescope sampling of all sub-arrays, on a hard-copy
   device.

   0>dev /ps
   0>tplot
   Page 01: Subarray 1
   Page 02: Subarray 2
   0>

   One page was plotted per sub-array to a postscript file.

3. Displaying telescope sampling of a single selected sub-array, on a
   hard-copy device.

   0>dev /ps
   0>tplot 3
   Page 01: Subarray 3
   0>

   A single page was plotted to a postscript file, showing telescope
   sampling in sub-array 3.

4. Starting the plot from sub-array 1 of IF 2.

   0>tplot 1, 2
   Move the cursor into the plot window and press 'H' for help

ARGUMENTS
---------
subarray    -    Default="" which selects all sub-arrays, starting from 1.
                 To start plotting at a specific sub-array, provide its
                 number here. The first sub-array is number 1. If the
                 output device is a non-interactive (eg. hard-copy)
```

```
                device then only this sub-array will be plotted.

IF_index    -   Default=The index of the first sampled IF.
                The index of the IF to plot first.

CONTEXT
-------
tplot plots the sampling of all telescopes, using one page per
sub-array and IF. Each telescope is assigned a line parallel to the
time axis of the plot. At the time-stamp of each integration, each
telescope whose visibilities have not been completely deleted is shown
as a dot. In general, each telescope is sampled on a number of
baselines per integration. If the visibilities to all those baselines
are not flagged, then the point is plotted in green. If some are
flagged but at least one is not flagged then orange is used, and if
all visibilities are flagged then the point is plotted either in red
or blue depending on whether the flagging is dominated by visibility
flags or by selfcal correction flags.

Note that what the visibilities that go into determining the flag
status of the plotted points, are those selected with the 'select'
command, rather than all visibilities in the observation.

INTERACTIVE MODE
----------------
If the device that you are plotting on possesses a cursor, then tplot
goes into an interactive mode. In this mode, move the cursor into the
plot area and press one of the following keys:

   H - (Help) Briefly list all keyboard options.

   X - Quit the tplot session, and return to the difmap prompt.

   L - Re-display the plot.

   N - Display the sampling of the next sub-array.

   P - Display the sampling of the previous sub-array.

   ] - Display sampling of the next IF.

   [ - Display sampling of the previous IF.

   T - Prompt for the next sub-array to be plotted. This is then
       entered by its numeric ID, at the keyboard.

   U - Select the time range to be plotted. Initially tplot plots
       sampling over the full range of integration times. To restrict
       the range press U, move the cursor to the start of the new
       range and press A (left mouse button), then move the cursor to
```

```
      the end of the required range and press A again. Sampling of
      the current sub-array will be re-plotted within the new range.
      To return to the full time range press U twice in succession.

   B - Break the displayed time range into scans. A scan is defined as
      a block of data, separated from the next block of data by more
      than an hour (this can be changed with the 'scangap' command).
      If there are no gaps this large then no change in plotting will
      result. Otherwise, each scan will be plotted within its own box
      and the gaps between scans will no longer be plotted. Scan mode
      will remain in effect until B is pressed again.

   C - Flag any un-flagged samples within a given area (see below).

   R - Restore any flagged samples within a given area (see below).

   W - Toggle the scope of edits with respect to spectral-line
      channels. Each plotted point comes from a single IF, and
      its displayed flag status is determined from the combined
      status of all the channels currently selected from that IF on
      each baseline of the telescope being sampled. By default, if
      you select such a point to be flagged, then all spectral-line
      channels of the source IF will be flagged for each of the
      effected baselines, irrespective of the channels which actually
      went into making the plot. The alternative is to edit just the
      channels that went into making the plot. The 'W' key toggles
      which of the two options is used, and a mode line above the
      plot describes which option is currently in effect.

   + - This key toggles whether the cursor is shown as a small cross
      or as a cross-hair that extends the full width and height of
      the display. Currently only the /xserve and /xwindow PGPLOT
      devices support this feature.

EDITING
-------
The Clip and Restore keys, 'C 'and 'R' enable you to edit all points
inside a rectangular box selected with the cursor. With the 'C'
option, all visibilities related to the selected stations over the
selected integrations are flagged. Similarly, the 'R' option unflags
all related visibilities in the area. To use these facilities, press
the respective key and then move the cursor to one corner of the
required region and press 'A' (left mouse button). Then move the
cursor to the opposite corner of the required region and again press
'A'. The display will be updated to show the results.

Examples of how one might use this facility include, removing a whole
scan at a time for all telescopes, or flagging a bad station over the
whole time range.
```

```
Also see the description of the 'W' toggle, which determines whether
to restrict the edits to the channels that went into making the plot,
or whether to edit all channels of the displayed IF.

RELATED COMMANDS
----------------
scangap  -   Change the time gap used to delimit neighboring scans.
radplot  -   Display visibility amplitude/phase vs. UV radius.
projplot -   Display visibility amplitude/phase vs. projected UV distance.
uvplot   -   Display the sampling of the UV plane.
vplot    -   Display observed and model visibilities from the current IF.
cpplot   -   Display observed and model closure phases interactively.
corplot  -   Display the self-cal corrections of the current IF.
```

uncalib

```
Undo recorded telescope calibrations (eg. self-cal corrections).

  uncalib dophase, doamp, doflag

EXAMPLE
-------

1. To remove all phase corrections amplitude corrections and correction
   flags, type:

   0>uncal true,true,true
   uncal: All telescope phase corrections have been un-done.
   uncal: All telescope amplitude corrections have been un-done.
   uncal: All telescope correction flags have been un-done.
   0>

2. To remove just amplitude corrections, while leaving selfcal correction
   flags and phase corrections in place, type:

   0>uncal false,true
   uncal: All telescope amplitude corrections have been un-done.
   0>

All but the first line are messages from 'uncalib'.

PARAMETERS
----------
dophase - If true then undo telescope phase calibrations (Default=false).

doamp   - If true then undo telescope amplitude calibrations (Default=false).

doflag  - If true, then remove all telescope correction flags (Default=false).

CONTEXT
-------
Contained in every data-set is the list of integration based telescope
amplitude and phase corrections per sub-array and IF, that have been
applied to the data. These corrections are incrementally updated
whenever further telescope based calibrations are applied, such as
when 'selfcal' is applied. By running the 'uncalib' command it is
possible to undo the effects of either or both of the amplitude and
phase calibrations. It is thus easy to go back to the un-calibrated
data-set or undo the effects of a badly constrained self-calibration.
Note that this removes the effects of ALL previous self-calibrations
etc.. It is also possible to remove all visibility flags applied by
selfcal without effecting normal visibility flags.

SIDE EFFECTS
```

```
------------
The current residual map is invalidated by the data modification,
so the next map oriented task invokes 'invert'.

RELATED COMMANDS
----------------
selfcal   - Self-calibrate data with the current model.
corplot   - Display and allow editing of corrections.
```

unshift

Undo accumulated position shifts from the data, windows and models.

```
  unshift
```

EXAMPLE

```
0>unshift
unshift: Removing accumulated position shifts.
0>
```

CONTEXT

The 'shift' command can be used to incrementally shift the position of the phase center of the data, and the associated positions of models and CLEAN windows. The 'unshift' command puts the data back to the position that they had when the observation was read into difmap.

ASSOCIATED COMMANDS
----

shift - Shift the observation phase-center, CLEAN window and model positions.

uvaver

```
Time average a UV data set.

  uvaver aver_time, doscatter

EXAMPLE
-------

0>uvaver 240
Averaging into 240 second bins.
Selecting channels: 1 -> 1, polarization: RR.
0>

All but the first line above are informational messages from the
'uvaver' command.

PARAMETERS
----------
aver_time - The duration of the new integrations in seconds.

doscatter - Default: FALSE
            If doscatter=FALSE then the new visibility weights will be
            the sum of the old visibility weights. This is
            statistically correct under the assumption that the input
            weights equal or are proportional to the reciprocal of the
            amplitude variance. This assumption is based on the rules
            described in AIPS documentation for UV FITS files.

            If doscatter=TRUE then the new visibilities will be
            given weights derived from the data by using the scatter
            within a solution interval to derive an estimate of the
            reciprocal amplitude variance. Effective use of this
            option requires that each output bin encompass many input
            integrations. In particular, if only one visibility exists
            in a given bin, uvaver will leave this visibility in place
            with its original weight, but make it flagged.

CONTEXT
-------

There are two main things that people commonly use uvaver for. The
obvious one is to reduce redundantly high time sampling. This speeds
up subsequent processing. The less obvious use is to re-bin the
data. This is useful if the data that were read in from a FITS file
had different time-stamps on different baselines within the same
logical integration. In this case when difmap reads such a file
the end result is that each baseline is assigned its own integration!
Not only does this waste large amounts of memory and subsequent CPU
time, but it also means that station-based editing in vplot actually
```

does baseline-based editing, and selfcal, when run without a solution time will not make any corrections due to the lack data within each integration. The solution is to re-bin the data into integrations with selfcal.

You should be careful to choose an averaging time, that will not smooth over real variations in the UV data. If you choose too large a time scale, large scale structures will disappear from your map.

CAUTION: *** If uvaver fails you may loose your data ***

When difmap reads a UV FITS file, it places the raw visibilities in a scratch file. This file is then read whenever the 'select' command is invoked, or when edits need to be applied. The uvaver command averages data in this file and writes the averaged integrations to a new scratch file before deleting the original. If it fails to write the new scratch file - perhaps because of insufficient disk space, then difmap will discard the current data. Thus you should check that you have sufficient disk space for the new file (look at the existing file called uvdata.scr to get an idea of the required disk space) before running uvaver. If you have done anything significant to the data, then it would also be prudent to save the merge file before running uvaver.

DETAILS

The uvaver command reads raw integration records from its existing uvdata scratch file and writes binned averaged integrations to a new uvdata file. When all integrations have been averaged, the old uvdata scratch file is deleted to be replaced by the new one.

For each new integration read within a given solution bin, uvaver adds to a weighted vector running mean of the data versus time and a weighted running mean of baseline U,V,W coordinates versus time.
As each solution bin is completed the averaged integration record is written to the output uvdata scratch file. The new U,V,W coordinates and time-stamps are recorded in memory as before.

Solution bins are regularly spaced on a grid of width equal to the averaging time. Input integrations are binned onto this grid.

uvplot

Plot observed UV points on the UV plane.

```
  uvplot station, umax, vmax, docursor
```

EXAMPLE

```
0> uvplot "BONN"
0>
```

This example plots the positions of visibilities in the UV plane, plotting all but the data associated with BONN in green. BONN data from the first sub-array is plotted in a different color to highlight it. If the display device has a cursor then interactive mode will be invoked after the initial display has been completed.

PARAMETERS
----

station - (Optional) The name of a station to highlight in the plot. If not given or given as an empty string "", no station will initially be highlighted. (Stations can be specified subsequently with the cursor).

umax - (Optional) Default=0 (0 -specifies the whole range). The maximum U coordinate to display. The plot will go from -umin to +umin. Unless changed with the mapunits command, the units are million-wavelengths.

vmax - (Optional) Default=0 (0 -specifies the whole range). The maximum V coordinate to display. The plot will go from -vmin to +vmin. Unless changed with the mapunits command, the units are million-wavelengths.

docursor - (Optional) Default=TRUE. If the display device has a cursor but you don't want to enter the interactive cursor mode, make this FALSE.

CONTEXT

This task displays the UV coverage of all un-flagged visibilities selected with the 'select' command. For each baseline, one point is plotted per IF. Where multiple spectral-line channels are selected from a given IF, the visibility is the average of those channels and is displayed at the corresponding mean U and V coordinates.

INTERACTIVE MODE

If your display device has a cursor, then there are a number of interactive options that you can use. These are selected by moving the cursor into the plot window, and pressing the following keys:

X - Quit the uvplot session, and return to the difmap prompt.

L - Re-display the plot.

Z - Zoom in on a rectangular sub-plot of the displayed region. After pressing 'Z' either press 'Z' again to revert to the original un-zoomed display, or select the two vertexes of the desired sub-plot area by sequentially pressing the 'A' key (left-mouse-button) over each. To cancel an incomplete selection, press 'D' (middle-mouse-button).

. - Toggle the marker symbol used to display the data between the smallest available and the next largest. By default the smallest possible marker symbol is used for speed, but if if the data are sparse then the larger marker symbol may be more convenient.

H - (Help) Briefly list all keyboard options.

n - Highlight visibilities from the next telescope in the currently highlighted sub-array. Initially no telescope is highlighted. If this key then pressed, the visibilities of the first telescope of the first sub-array will be highlighted. Pressing this key again highlights the second telescope, etc.. When the last telescope of the current sub-array has been plotted, the first telescope of the next sub-array will be plotted. So by repeatedly pressing this key you will eventually have seen each telescope of all sub-arrays individually highlighted.

p - This has the reverse the effect to the 'n' key, highlighting the visibilities of the previous telescope in the current sub-array, and wrapping back to the last telescope in the previous sub-array, after the first telescope of the current sub-array is highlighted.

N - [Upper-case n] Similar to the lower-case 'n' key this key results in the first telescope of the next sub-array in the observation to be highlighted. In this way you can jump between sub-arrays without having to see all the telescopes of the intermediate sub-arrays highlighted one at a time.

P - [Upper-case p] This has the reverse effect of the 'N' key, allowing one to directly step backwards through sub-arrays.

```
   T - To have a specific telescope of a specific sub-array
       highlighted without having to step through all the intermediate
       telescopes and sub-arrays, press this key. On the text window
       you will then be prompted for the name of the telescope to be
       highlighted. Telescopes are specified by an optional sub-array
       number delimited by a colon, followed by an unambiguous
       telescope name prefix.  If the sub-array number and colon are
       omitted then the sub-array from which telescopes are currently
       being highlighted will be assumed. For instance, both
       3:BONN and BON refer to a telescope named BONN in sub-array 3
       if another telescope of sub-array 3 is currently being
       highlighted. Also, provided that sub-array 2 does not contain
       more than one telescope starting with the prefix JBN, 2:JBN is
       sufficient to refer to a telescope called JBNK1 in sub-array 2.

   S  - This causes uvplot to display details about the visibility
       nearest to the cursor. It shows the sub-array, baseline,
       IF number and date of the visibility.

   C  - This initiates cut area selection, through which a rectangular
       area may be selected within which to flag data. After pressing
       'C' you will be expected to enter the locations of two opposite
       corners of the area, by pressing 'A' (left-mouse-button) over
       the corresponding points of the plot. To cancel a half selected
       area press 'D' (central-mouse-button). Once two corners have
       been selected, all visibilities displayed in that area will be
       flagged and will then disappear from the plot.

   W  - Toggle the scope of edits with respect to spectral-line
       channels. Each point in the plot comes from a single IF, and
       its position in the plot is determined by the mean frequency of
       the channels currently selected from that IF. By default, if
       you select such a point to be flagged, then all spectral-line
       channels of the source IF will be flagged, irrespective of the
       channels which actually went into making the plot. The
       alternative is to edit just the channels that went into making
       the plot. The 'W' key toggles which of the two options is used,
       and a mode line above the plot describes which option is
       currently in effect.

   +  - Toggle whether the cursor is shown as a small cross or a
       cross-hair that extends the full width and height of the display.
       Currently only the /xserv and /xwin PGPLOT devices support this
       feature.

OTHER DISPLAY COMMANDS
----------------------
radplot  -   Display visibility amplitude vs. radius.
projplot -   Display visibility amplitude/phase vs. projected UV distance.
```

```
vplot    -   Display observed and model visibilities from the current IF.
tplot    -   Display the time-sampling of each telescope of the current IF.
corplot  -   Display the self-cal corrections of the current IF.
cpplot   -   Display observed and model closure phases interactively.
```

uvrange

```
Set the min and max UV radii of usable visibilities for gridding.

  uvrange uvmin, uvmax

EXAMPLE
-------

0>uvrange 0.1,10
Only data in the UV range: 0.1 -> 10 (mega-wavelengths) will be gridded.
0>

The second line is the response from the 'uvrange' command, confirming
the user's selection. To see what the currently assigned range is, type:

0>uvrange
Only data in the UV range: 0.1 -> 10 (mega-wavelengths) will be gridded.
0>

To cancel a previously selected range, type:

0>uvrange 0,0
The full UV range of the data is currently selected for gridding.
0>

PARAMETERS
----------

uvmin - The minimum UV radius from which visibilities will be used
        during gridding. Unless changed with the mapunits command, the
        units are million-wavelengths.

uvmax - The maximum UV radius from which visibilities will be used
        during gridding. Unless changed with the mapunits command, the
        units are million-wavelengths.

If uvmax <= 0 or uvmin < 0 or uvmax < uvmin, no select range is
applied and any previous select range is cancelled.

eg.  'uvrange 0,0'  cancels any previous select range.

Whenever a new UV data set is read with the 'observe' command, any
existing values of uvmin and uvmax are discarded.

CONTEXT
-------
This function effects subsequent invokations of the 'invert' command.
The select range remains in force until this command is called again,
or until a new data-set is read with the 'observe' command.
```

```
The range is applied during 'invert', such that all visibilities whose
radial distance in the UV plane exceeds uvmax, or is less that uvmin,
are excluded from gridding, prior to Fourier inverting the map and
beam into the image plane.

SIDE EFFECTS
------------
Use of this command will cause the next 'clean', 'mapplot' etc..
to re-invert the modified UV data-set to produce an updated dirty
beam and residual map.

RELATED COMMANDS
----------------
uvtaper  - Apply a gaussian taper to the gridding weights.
uvweight - Selects combinations of natural,uniform, uncertainty, and
           radial weighting.
uvrange  - Constrain the min and max UV radii within which visibilities
           are gridded.
uvzero   - Set a zero-UV-spacing flux.
```

uvstat

```
Return UV plane visibility statistics.

  uvstat statistic

EXAMPLE
-------

 0>print uvstat(rms)
 0.333969
 0>
 0>print uvstat(chisq)
 1.07537
 0>
 0>print uvstat(nvis)
 10756
 0>

PARAMETERS
----------

statistic  -  The name of the statistic wanted. Recognised names are:

               rms   -   The root-mean-square difference between observed
                         and model visibilities (Jy).
               chisq -   The reduced chi-squared fit between the
                         observed and model visibilities.
               nvis  -   The number of un-flagged visibilities.

CONTEXT
-------
This function provides access to a few statistics relating model and
observed visibilities in the UV plane. The return value may be used in
expressions, and thus may be used in automatic mapping procedures.

SIDE EFFECTS
------------
The tentative model will be established in the UV plane if not already
there. This in turn will force difmap to re-invert the data before the
next operation that involves the current map.

RELATED COMMANDS
----------------
imstat - Return image plane map statistics.
```

uvtaper

```
Set a gaussian taper to weight down long baselines and reduce sidelobes

  uvtaper gaussian_value, gaussian_radius

EXAMPLE
-------

0>uvtaper 0.5,10
Gaussian taper: value 0.5 at UV radius = 10 Mega-wavelengths
0>

The second line is the response from the 'uvtaper' command, confirming
the selection made by the user. To see what the current values are
without changing them:

0>uvtaper
Gaussian taper: value 0.5 at UV radius = 10 mega-wavelengths.
0>

To cancel a previously set taper type:

0>uvtap 0
No UV-taper is currently set.
0>

PARAMETERS
----------
gaussian_value  - The value of the gaussian taper at 'gaussian_radius'.
                  Valid values lie between 0 -> 1 exclusive. Other
                  values cause the cancellation of any existing gaussian
                  taper.
gaussian_radius - The UV radius at which gaussian taper should have
                  fallen to 'gaussian_value'. (values <= 0 de-select
                  gaussian tapering). Unless changed with the mapunits
                  command, the units are million-wavelengths.

To cancel a previous gaussian taper you should type: uvtaper 0
Whenever a new UV data set is read with the 'observe' command
any existing gaussian taper is cancelled.

CONTEXT
-------
Before the visibilities are inverted to the image plane they are first
gridded. In the process of gridding, individual visibilities are
weighted. Gaussian tapering can be applied in addition to the other forms
of weighting specified with command 'uvweight'. It is generally used
to weight down long baselines in order to increase the signal to noise
ratio of low-surface brightness, extended emission or to reduce
```

```
side-lobes during the initial stages of mapping. It does this at the
expense of spatial resolution. The taper selected remains in force
for use by all subsequent uses of the 'invert' command, until 'uvtaper'
is used again to change or cancel the taper.

SIDE EFFECTS
------------
Use of this command will cause the next 'clean', 'mapplot' etc..
to re-invert the modified UV data-set to produce an updated dirty
beam and residual map.

RELATED COMMANDS
----------------
uvweight - Selects combinations of natural,uniform, uncertainty, and
           radial weighting.
uvrange  - Constrain the min and max UV radii within which visibilities
           are gridded.
uvzero   - Set a zero-UV-spacing flux.
```

uvweight

Set the type and degree of weighting for subsequent UV gridding.

```
  uvweight bin_size, error_power, do_radial
```

EXAMPLE
----

1. To select uniform weighting and to scale the uniform weighting grid
   weights by the errors implied by the data raised to the power -1, type:

```
   0>uvweight 2,-1
   Uniform weighting binwidth: 2 (pixels).
   Gridding weights will be scaled by errors raised to the power -1.
   Radial weighting is not currently selected.
   0>
```

   The first line illustrates a typical use of the command, and the
   following three lines are the response by the 'uvweight' function,
   confirming the choices made.

2. To see the current choice of weighting, omit all arguments:

```
   0>uvweight
   Uniform weighting binwidth: 2 (pixels).
   Gridding weights will be scaled by errors raised to the power -1.
   Radial weighting is not currently selected.
   0>
```

PARAMETERS
----

bin_size - If this is > 0 then it selects uniform weighting. The
            value sets the bin size in UV-grid pixels within which to
            count neighboring visibilities. The reciprocal of these
            counts are then used to weight the visibilities by the
            local number density. A value of 2 is recommended.
            Non-integral values are legal but fractional values below
            1 are not.

error_pow - If < 0 then this selects additional weighting by amplitude
            errors. The value selects the exponent to raise the error
            to. Statistically this should be -2, but -1 is recommended.
            Make sure that the relative errors between baselines are
            meaningful before using this option or you may end up with
            some baselines making no contribution to the final map!

do_radial - If true then the weight given to each visibility will be
            divided by its UV radius. Only recommended when one's
            UV coverage is approximately circular.

```
CONTEXT
-------
This command sets the weights given to individual visibilities as they
are gridded, prior to Fourier inversion into the image plane. The
choices made remain in effect until this function is called again.

When a new data set is read with the 'observe' command, the defaults
are reset to apply uniform weighting with a bin-width of 2 and no
other form of weighting.

Unless the commands mentioned in the last section are of interest, you
would typically follow this command by invoking the 'invert' command.
(See help on 'invert' for details).

SIDE EFFECTS
------------
Use of this command will cause the next 'clean', 'mapplot' etc..
to re-invert the modified UV data-set to produce an updated dirty
beam and residual map.

RELATED COMMANDS
----------------
uvtaper - Apply a gaussian taper to the weights.
uvrange - Constrain the min and max UV radii within which visibilities
          are gridded.
uvzero  - Set a zero-UV-spacing flux.
```

uvzero

Set the estimated flux expected from a baseline of zero length.

```
  uvzero flux, weight
```

EXAMPLE

```
0>uvzero 10, 100
Zero-baseline flux set to 10 Jy. Weight=100.
0>
```

The second line is the response from the 'uvzero' command, confirming the user's selection. To see the value of the current zero-spacing flux omit all arguments:

```
0>uvzero
Zero-baseline flux set to 10 Jy. Weight=100.
0>
```

To cancel a previously set zero-baseline flux spefiy zero.

```
0>uvzero 0,0
Zero-baseline flux not set.
0>
```

PARAMETER
----

flux - The estimated total flux of the observation (Jy). This will be treated as though it were the flux density of a normal visibility at U=0 and V=0.

weight - The visibility weight to be assigned to the zero-baseline flux. This is the weight to be seen after application of wtscale and has the same form as the weights of normal visibilities. However note that the addition of a zero-baseline visibility is like the addition of a single extra sample in the UV plane and will have very little effect unless a large weight is used.

Whenever a new UV data set is read with the 'observe' command, the default value of flux=0.0 is set.

CONTEXT

If an observation is so defficient in short baselines that no value is added to the pixel at the origin of the U,V plane grid, then the total flux in the dirty map will equal zero (as required by Fourier transform theory). For very extended sources this may result in low brightness regions of the source appearing to be negative because the

flux in every pixel of the map is offset by a small negative amount. The effect may be countered to some extent by adding a fake visibility at the origin of the UV plane. Unfortunately, while the total estimated flux of the source can be used to set the amplitude of the visibility and the phase at the origin is known to be zero, the weight to give the visibility is a matter of experimentation. A weight value that is much higher than the average weight of the observed visibilities will be needed if any effect is to be seen. The best value will depend on the distribution of the observed visibilities and their weights.

In practice it is probably easier to get rid of negative bowls by model fitting rather than experimenting with the zero-spacing flux.

SIDE EFFECTS

Use of this command will cause the next 'clean', 'mapplot' etc.. to re-invert the modified UV data-set to produce an updated dirty beam and residual map.

vplot

General visibility plotting and editing command.

```
  vplot nplots, reftel, IF_index, npage
```

PARAMETERS
---

nplots - (Optional) Default=0 (All baselines to each station).
The number of baselines to be displayed per page. This may be changed interactively. Since only the baselines of one station are displayed on one page, the maximum number of plots per page at a given time is 1 less than the number of stations in the sub-array being displayed.

reftel - (Optional) Default=""
A baseline specification or the form

```
 [sub-array-index:][antenna_name_1][ antenna_name_2]
```

On interactive devices this specifies which baseline should be plotted first. On non-interactive devices it specifies the range of baselines to be plotted. For instance on a non-interactive device "1:" means plot all baselines of sub-array 1, whereas on an interactive device, it means, start plotting baselines for the first available antenna of sub-array 1. For further details of baseline specifications, read the antenna_names help topic.

IF_index - (Optional) Default = The first sampled IF.
The index of the IF to start plotting visibilities from.

npage - (Optional) Default = 0 (with requests no page limit).
The maximum number of pages to plot when plotting to a non-interactive device.

CONFIGURATION VARIABLES
---

vflags - This is a string variable that over-rides the default display attributes. It is particularly useful when displaying to a hard-copy device, where interactive changes to the default attributes can not be made.

By default vflags="". In this case vplot substitutes the equivalent of vflags="efmb3".

When vflags is not "", all toggled attributes are initially set to off, and the contents of the vflags string determine which of the

attributes get turned back on.

The entries in the vflags string are the keys used in interactive mode to toggle the respective attributes on and off, and are interpretted exactly as though you had pressed them interactively. This means that if an option appears twice in vflags the second instance cancels the first! The available keys are listed further below.

For example after typing:

vflags="efm1"

Subsequent use of vplot after typing this will initially plot visibilities with error-bars (e), will show flagged-data (f), will show the model (m), and only display amplitudes (1).

CONTEXT

This command can be used in non-interactive mode to display visibility data on a hard-copy device, or interactively to examine and/or edit visibilities.

When displayed, flagged data appear as red '+' symbols, un-flagged data as green points and the model as a continuous light-blue line. In addition, if a visibility is flagged by a selfcal correction flag, but not by a normal visibility flag, it is displayed as a blue 'x' symbol.

Only visibilities from a single IF are displayed at one time, but the selected IF can be changed interactively, or preset on the command line.

HARD COPY MODE

If this command is invoked when the PGPLOT output device is a hard-copy device, such as a laser printer, one can specify which baselines to plot and how to arrange them. This is illustrated in the following examples:

1. Plot all of the baselines in the observation, grouped by telescope name and sub-array, displaying 5 baselines per page. This could take some time so be prepared to wait.

   0> vplot 5

2. Plot all baselines from sub-array 1, at 5 baselines per page.

   0> vplot 5, 1

3. Plot all HSTK baselines of sub-array 2 in IF 3, again at 5 baselines per page.

```
   0> vplot 5, 2:HSTK, 3
```

4. Plot all HSTK baselines of sub-array 2, starting from baseline HSTK-BONN, using as many plots per page as there are telescopes in sub-array 2 (minus 1).

```
   0> vplot 0, 2:hstk bonn
```

```
INTERACTIVE MODE
----------------
If the display device has a cursor, then an interactive session will
be invoked. In this mode, one page of baselines is initially plotted
and mouse-keys and keyboard keys are used to guide the task through
plotting and data editing.

Once vplot has been invoked, move the cursor into the display window
and press the 'H' key on your keyboard. Whenever this is pressed
during the vplot session a list of key bindings will be displayed in
the terminal window from which vplot was invoked.

Most keys are case-insensitive, such that both 'H' and 'h' have the
same effect.

On standard PGPLOT conforming devices with a mouse or other cursor
control device, mouse buttons are treated as equivalent to the
following keyboard keys:

Left button   = 'A'   (This is the normal key for selecting positions).
Middle button = 'D'   (This is used to cancel incomplete select ranges).
Right button  = 'X'   (Use this to exit vplot).

Note that on a windowing system, the cursor must be within the display
window before pressing keyboard keys (and mouse buttons) will be
noticed. However, after pressing a key that needs more complex
answers, such as the entry of the number of baselines to display or
the entry of a telescope name, the cursor should be moved to the
original text window where a prompt will be displayed to guide your
entry.

MOVING ABOUT BETWEEN BASELINES
------------------------------

 n - (Lower-case n) Display next set of baselines
 p - (Lower-case p) Display preceding set of baselines

Pressing 'n' in vplot causes the Next set of baselines of the current
telescope to be displayed from the current sub-array. Once all
baselines to that telescope have been displayed, pressing 'n' will
proceed to display those of the next telescope in the observation.
```

Once all telescopes have been displayed in this manner, pressing 'n' will display start to display baselines from the next sub-array. So by repeatedly pressing 'n' you will see all baselines in every sub-array of the observation. The 'p' key works identically but shows the Previous set of baselines.

N - (Upper-case n) Display baselines from the next sub-array.
P - (Upper-case p) Display baselines from the previous sub-array.

Upper-case 'N' and 'P' provide a means to jump to the next or previous sub-arrays without having to view all of the intermediate baselines.

T - Specify reference telescope from the keyboard (text screen)

To move to another telescope without having to wade through all the baselines of previous telescopes in the observation, press 'T'. Back on the text screen you will be prompted for the name of the telescope. The name entered may be any unambiguous abbreviation of the full telescope name.

eg BOLOGNA and BONN are ambiguous up to BO. BOL or BON are the shortest names that could be used to refer to them.

A optional second telescope name may also be entered on the same input line, separated from the first by spaces or a hyphen, in which case the combination of the two telescope names will be used to designate the first baseline to be displayed to the new reference telescope.

If the required telescope(s) are from a different sub-array than the one currently being displayed, then specify the sub-array number preceding the first telescope name and separated from it with a colon. Thus BONN-BOL selects baseline BONN-BOLOGNA in the currently displayed sub-array, while 3:BONN-BOL selects baseline BONN-BOLOGNA in sub-array 3.

MOVING BETWEEN IFs

Visibilities are only displayed from one IF at a time. The identity of this IF is displayed above the collection of plots. To move onto the next or previous IF in which any channels were selected with the 'select' command, use the following keys:

] - Move to the next sampled IF.
[- Move to the previous sampled IF.

The title above the plots will change to indicate which IF is being displayed.

CHANGING HOW BASELINES ARE DISPLAYED

```
The following keys toggle attributes on or off. The display will
not be re-plotted immediately whenever one of these is toggled, so
you can press a sequence of toggle keys before re-displaying with
the new attributes. When the sequence is complete, simply press
any key that is not in the list below, such as the RETURN key
and the display will be updated with the new attributes.

 M - Toggle display of model visibilities
 F - Toggle display of flagged visibilities
 E - Toggle display of error bars
 1 - Plot only amplitudes.
 2 - Plot only phases.
 3 - Plot both amplitudes and phases.
 B - Toggle breaking the plot into scans (where present)
 V - Toggle inclusion of flagged data in auto-scaling

NB. By default, a scan is taken to be any set of integrations which is
    separated by more than an hour from its nearest neighbors. This
    can be changed with the 'scangap' command.

CHANGING THE NUMBER OF BASELINES DISPLAYED
------------------------------------------

 S - Select number of sub-plots per page

To change the number of baselines displayed, press the 'S' key.
You will be prompted for a number on the text screen. The first
baseline plotted will be the same as before, but only the requested
number will follow.

CHANGING THE DISPLAYED UT RANGE
-------------------------------

 U - select UT range to be displayed (hit U twice for full range)

Press 'U' to request a change in the displayed UT range. You will
then be expected either to press 'U' again to display the whole
UT range, or to move the cursor to the start UT of the required
range and press 'A' (left mouse button), then move the cursor to
the end UT of the required range and press 'A' again. The plot
will then be re-displayed over the new range and all subsequent
plots will be displayed over this range. At any point before
the UT range selection has been completed, pressing the 'D' key
(middle mouse button) will quietly abort the selection.

CHANGING THE DISPLAYED AMPLITUDE OR PHASE RANGE
-----------------------------------------------

 Z - Select amplitude or phase range to be displayed.
```

Press 'Z' to zoom in on a selected amplitude or phase range.
You should then either to press 'Z' again to revert to the default
range, or move the cursor to the first (top or bottom) amplitude or
phase value of the required vertical range and press 'A'
(left mouse button), then move the cursor up or down to the end
of the required range and press 'A' again. The plot will then be
re-displayed over the new range and all subsequent plots will be
displayed over this range. At any point before the selection has been
completed, pressing the 'D' key (middle mouse button) will quietly
abort the selection.

CHANGING WHETHER REDUNDANT BASELINES ARE DISPLAYED

By default, for each reference telescope that it plots, vplot displays
all of the baselines that include that telescope. This is recommended
because it aids in finding telescope dependent errors. However, it
does result in you seeing each baseline twice if you step through all
antennas. This can be annoying if you have a very large number of
baselines. For this reason vplot also provides the option to only show
each baseline once, by only showing baselines in which the second
antenna of the baseline comes later in the antenna listing than the
reference antenna. Thus for the first antenna you see all of the
baselines for that antenna, but for the second you see one less
baseline, and so on, until by the time you reach the last antenna,
there are no baselines to be plotted.

  O - Toggle telescope ordering to only show non-redundant baselines.

EDITING DATA

There are two main modes for editing and it is important to select
the right one before proceeding.

Station based edits flag or un-flag the selected visibilities on
ALL baselines that include the current reference telescope. If you
have more than one baseline displayed at a time, then this will be
evident, as the selected visibilities will change color on all the
displayed baselines.

Baseline based editing only affects the baseline in which the
selection was made.

   - (SPACE BAR) Toggles station based vs. baseline based editing.

The current editing mode is displayed above the plots on the
right-hand side of the display and can be toggled by pressing the
SPACE-BAR.

It is also possible to further specify the scope of edits.

```
 I - Toggle IF editing scope.
 W - Toggle spectral-line editing scope.

By default, edits are applied to all polarizations, spectral-line
channels and IFs related to the selected visibility. To specify that
edits only be applied to the displayed IF, press the 'I' key. To
specify that edits be only applied to the channels that were specified
with the 'select' command, press the 'W' key. The mode line above the
collection of plots, describes which of these editing modes is in
effect.

 A - Flag or unflag the nearest visibility to the cursor.
     (Left mouse button)

Pressing 'A' on the keyboard or the left mouse button near a displayed
visibility point causes the status of that visibility to be toggled
from un-flagged to flagged or vice versa. If flagged data are displayed,
then toggling an un-flagged visibility will produce a red cross
signifying its new flagged status. Otherwise the point will magically
disappear, but can be seen subsequently if the display of flagged data
is enabled.

 C - Flag all data inside select box
 R - Restore data inside select box

If you wish to flag or un-flag an extended region of data, point by
point editing is tedious. The Clip and Restore keys, 'C 'and 'R'
enable you to edit all points inside a square box selected with the
cursor. To use this facility, press the respective key and then
move the cursor to one corner of the required region and press 'A'
(left mouse button). Then move the cursor to the opposite corner of
the required region and again press 'A'. The selected points will be
re-displayed with their changed statuses. Note that it is especially
important to know whether station or baseline based editing is
required before doing this since in station based editing restoring a
region that you have just clipped may restore points on related
baselines that were originally clipped for other reasons.

FLAGGING A WHOLE SCAN
---------------------
To flag a whole scan on a given baseline, move the cursor into the
selected scan on the baseline to be edited and press the 'Z' (ie. zap)
key. All points on that baseline within the scan will be flagged, even
those not in the currently displayed UT range. In this context a scan
is either a single scan obtained after using the 'B'
(break-into-scans) key, or the whole UT time range otherwise.
Note that the current station/baseline editing mode has no effect on
the behavior of this command - so only one baseline will be flagged
at a time.
```

```
ENDING A vplot SESSION
----------------------
To end a vplot session, press 'X' or the right mouse button.
If substantial editing was performed in vplot then it is advisable to
use the wmerge command to save the modified file before continuing
to map the data.

MISCELLANEOUS features
----------------------
The following interactive key bindings have not bee discussed above.

 L - When you press this key the current plot is re-displayed.

 + - This key toggles whether the cursor is shown as a small cross or
     as a cross-hair that extends the full width and height of the
     display. Currently only the /xserve and /xwindow PGPLOT devices
     support this feature.

RELATED COMMANDS
----------------
scangap  -   Change the time gap used to delimit neighboring scans.
radplot  -   Display visibility amplitude vs. UV radius.
projplot -   Display visibility amplitude/phase vs. projected UV distance.
uvplot   -   Display the sampling of the UV plane.
tplot    -   Display the time-sampling of each telescope.
corplot  -   Display accumulated self-calibration corrections.
cpplot   -   Display observed and model closure phases interactively.
```

wbeam

```
Save the dirty beam to a FITS file.

  wbeam file_name

EXAMPLES
--------

0>wbeam beam.fits
Writing dirty beam to FITS file: beam.fits
0>

PARAMETERS
----------
file_name - The file name to be given to the new FITS file.

CONTEXT
-------
'wbeam' can be used to save the restored beam to a FITS file at any
point during mapping. Many other programs, such as AIPS can read such
files.

The whole area of the beam grid is saved.

RELATED COMMANDS
----------------
wmap   - Write the clean (restored) map to a FITS file.
wdmap  - Save the dirty (residual) map.
wobs   - Write the UV data to a random-groups UV FITS file.
wmodel - Write the CLEAN model to a (text) VLBI model file.
wwins  - Write CLEAN windows to a text file.
save   - Save UV data, models, windows and the restored map.
```

wdmap

```
Save the residual dirty map to a FITS file.

  wdmap file_name

EXAMPLES
--------

0>wdmap dirty.fits
Writing dirty map to FITS file: dirty.fits
0>

PARAMETERS
----------
file_name - The file name to be given to the new FITS file.

CONTEXT
-------
'wdmap' can be used to save the residual dirty map to a FITS file at
any point during mapping. Many other programs, such as AIPS can read
such files. If necessary the map will be inverted first. If a model
exists then it is also recorded in an 'AIPS CC' binary extension
table.

Only the inner cleaned region (the same as the region that mapplot
displays by default) is saved to the file.

RELATED COMMANDS
----------------
wmap   - Saves the clean (restored) map.
wbeam  - Writes the dirty beam to a FITS file.
wobs   - Writes the UV data to a random-groups UV FITS file.
wmodel - Write the CLEAN model to a (text) VLBI model file.
wwins  - Write CLEAN windows to a text file.
save   - Save UV data, models, windows and the restored map.
```

winmod

```
Delete all components outside (or inside) the current clean windows.

  winmod discard_selected

EXAMPLE
-------

0>winmod
The latest clean model now contains 31 of the original 92 components.
The established clean model now contains 65 of the original 72 components.
0>

PARAMETERS
----------
discard_selected  -  (Default=false)
                     If false then discard all model points outside the
                     current clean windows.
                     If true then discard all model points inside the
                     current clean windows.

CONTEXT
-------
This command is intended for the situation where one finds that the
choice of clean windows in a previous clean allowed model components
to be placed in suspect positions. Running this command allows one to
constrain the model components to lie within the latest estimate
of the clean windows. You should beware of the fact that the components
so deleted may have had effects on the flux within the windows,
so run mapplot again after calling this command to see how the deleted
parts of the model effected the residual map and be prepared to
continue cleaning a bit further.

SIDE EFFECTS
------------
Use of this function will cause the next command that requires the
residual map, to re-invert it.

RELATED COMMANDS
----------------
mapplot - Use this to look at the model components as well as the map.
```

wmap

Save the clean (restored) map to a FITS file.

```
  wmap file_name
```

EXAMPLES

```
0>wmap map.fits
Writing clean map to FITS file: map.fits
0>
```

PARAMETERS
----
file_name - The file name to be given to the new FITS file.

CONTEXT

'wmap' can be used to save the restored map to a FITS file at any point during mapping. Many other programs, such as AIPS can read such files. If necessary the map will be restored first. The model used to restore the map is also recorded in an 'AIPS CC' binary extension table.

Only the inner cleaned region (the same as the region that mapplot displays by default) is saved to the file.

RELATED COMMANDS
----
wdmap - Save the dirty (residual) map.
wbeam - Write the dirty beam to a FITS file.
wobs   - Write the UV data to a random-groups UV FITS file.
wmodel - Write the CLEAN model to a (text) VLBI model file.
wwins - Write CLEAN windows to a text file.
save   - Save UV data, models, windows and the restored map.

wmodel

```
Write CLEAN models to a VLBI model file.

  wmodel file_name, do_continuum

EXAMPLE
-------

0>wmodel test.mod
Writing 26 model components to file: test.mod
0>

PARAMETERS
----------
file_name    - (Default=standard output)
               The name to be given to the new model file. If this
               argument is omitted or "" is specified, then the model
               will be displayed on the standard output and also in the
               log file.

do_continuum - (Default=false)
               If omitted or given as FALSE, the normal established and
               tentative models will be written. If it is given as TRUE,
               then just the continuum model (if any) will be written.

CONTEXT
-------
This command is used to save both the established followed by the
latest clean models in one file. On a later date the model can be
re-read using the 'rmodel' command and used as a starting model.

It can also be used to save the continuum model, if one exists, by
presenting the optional second argument with the value TRUE.

RELATED COMMANDS
----------------
rmodel - Read a new CLEAN model from a file.
save   - Save all data files and the difmap running parameters.
```

wobs

```
Save UV data to a random-groups UV FITS file.

  wobs file_name

EXAMPLE
-------

0>wobs 3c345.uvf
Writing UV FITS file: 3c345.uvf
0>

ARGUMENTS
---------
file_name  -  The name to give the new FITS file.

CONTEXT
-------
Once UV data have been read into difmap with the 'observe' command, it
may be saved to a new random-groups UV FITS file with the 'wobs'
command. If visibilities have been edited then the new file will
contain the edited data. Any edits that were applied in difmap, as
well as self-calibration and residual offset corrections, will be
applied to the saved data. This command is automatically called by the
'save' command.

RELATED COMMANDS
----------------
observe - Read a new random-groups UV FITS file.
wmap    - Write the clean (restored) map to a FITS file.
wdmap   - Save the dirty (residual) map.
wbeam   - Write the dirty beam to a FITS file.
wmodel  - Write the CLEAN model to a (text) VLBI model file.
wwins   - Write CLEAN windows to a text file.
save    - Save UV data, models, windows and the restored map.
```

wtscale

Change the scale factor that mutiplies the raw visibility weights.

```
  wtscale scale
```

EXAMPLE

```
0>wtscale
Current weight scale factor is: 1
0>
0>wtscale 15
Changed weight scale factor to: 15
0>
0>wtscale wtscale()*2.3
Current weight scale factor is: 15
Changed weight scale factor to: 34.5
0>
```

PARAMETERS
----

scale - The new scale factor to mulitply the raw visibility weights by. Note that increasing the weights corresponds to decreasing the apparent visibility amplitude uncertainties, and vice versa. In particular, to scale the error bars by a factor C, the argument of the wtscale command would have to be 1/C^2.

CONTEXT

In UV FITS files each visibility is given a weight that is proportional to the reciprocal of the associated visibility amplitude variance. Unfortunately the constant of proportionality that is optionally given in the same files, is rarely anywhere near the right magnitude, let alone correct. The two adverse results are that 'vplot' displays amplitude uncertainty error bars that are totally non-sensical, and that the self-calibration commands report scaled Chi-squared values that make it difficult to judge the significance of the fit.

The 'wtscale' command has been provided to enable one to change the scale factor. In some cases it is possible to deduce the appropriate weight scale factor by knowing where the data originated from, but in other cases getting the "right" factor is unfortunately a matter of guess work. Trial and error based on inspection of the error bars in 'vplot' is the only way to make this guess at the moment. Note that scaling the weights by X scales the error bars by 1/sqrt(X).

If the data-set is written back to a UV FITS file the weights will be left un-scaled, but the accumulated scale factor will be recorded via

the AIPS mechanism of writing a HISTORY line of the form:

HISTORY AIPS WTSCAL=....

Both AIPS and Difmap recognise such lines, so if the file is later read back into difmap or AIPS the weight scale factor will be corrctly recovered. Note that since history lines are written incrementally, there may be many history lines of the above form. The last such line is the one actually used.

VLA DATA

The VLA writes weights equal to the number of 10s intervals in an integration. The correct weight scale factor can be determined from the equation for the expected noise variance:

$$1/\text{variance} = (1e\text{-}26)^2 * \frac{Bw.t.(A.na.nc)^2}{2.0 * (k.Tsys)^2}$$

Boltzmann's contant : k = 1.38066e-23 J/K
System temperature : Tsys = 40K (typical for the VLA).
Observing bandwidth : Bw
Integration time : t = const * 10s
Antenna area : A = 490.8739 m^2
Antenna efficiency : na = 0.63
Correlator efficiency: nc

The correlator efficiency depends on the VLA observing mode, but is documented in the synthesis imaging workshop book.

Thus given that the raw data weights equal the number of 10 second intervals in an integration, the correct value of wtscale is:

$$\text{wtscale} = Bw * nc^2 * 1.5678e\text{-}4$$

Note that when used to combine two stokes parameters into a derived polarization (eg. RR+LL->I), AIPS SPLIT doesn't combine the weights correctly. If you are using data that have been processed in this fashion, the above wtscale factor should be scaled by a factor of 2. If you combine RR+LL->I with 'select' in difmap there is no need for this.

wwins

```
Save CLEAN windows to a text file.

  wwins winfile, do_old

EXAMPLE
-------

0>wwins "myfile.win"
wwins: Wrote 9 windows to myfile.win
0>

PARAMETERS
----------
winfile  -  (Default=standard output)
            The name to call the new window file. If this argument is
            omitted or "" is specified, then the windows will be
            displayed on the standard output and also in the log file.

do_old   -  (Default=FALSE)
            If TRUE then write the windows in the format required
            by the Caltech Package 'clean' program, ie.
            LRTB = n,n,n,n,....

CONTEXT
-------
CLEAN windows are set interactively in mapplot and/or directly via
the addwin command. The resulting list of windows may be saved to
a file using the 'wwins' command and retrieved later using the 'rwins'
command. This makes it possible to use the same windows for data at
a different epoch or to continue cleaning a data-set at a later date
using the same windows.

Please see help on rwins for a description of the default format used.

If do_old is specified as TRUE then the alternate format used by the
'clean' program in the Caltech VLBI Package is written. This format
can NOT be read back into difmap.

RELATED COMMANDS
----------------
rwins - Read previously saved CLEAN windows from a text file.
```

xyrange

Set the bounds of the sub-image to be displayed in mapplot.

```
  xyrange xa, xb, ya, yb
```

EXAMPLE

```
0>xyrange -10,20,0,0
The mapplot display area will be limited to:
 Relative  RA: -10 -> 20 (milli-arcsec)
 Relative DEC: (The whole available range)
0>
```

The second and subsequent lines are confirmatory messages
produced by the xyrange command.

PARAMETERS
----

xa - The X (center-relative RA) coordinate of one edge of the
required sub-image. Unless changed with the mapunits command,
the units are milli-arcsec.

xb - The X (center-relative RA) coordinate of the opposite edge of
the required sub-image to xa.

ya - The Y (center-relative DEC) coordinate of one edge of the
required sub-image. Unless changed with the mapunits command,
the units are milli-arcsec.

yb - The Y (center-relative DEC) coordinate (milli-arcsec) of the
opposite edge of the required sub-image to ya.

CONTEXT

By default, the whole available map or beam area is displayed when
you invoke mapplot. To change this behavior use the xyrange command
to select the required sub-image for subsequent calls to mapplot.
Alternatively, the displayed area can be changed interactively with
the cursor and optionally saved (as though xyrange had been called)
for later calls to mapplot - see help mapplot.

RELATED COMMANDS

```
mapplot  -  Display map and beam images.
loglevs  -  Set logarithmic contour levels for mapplot.
xyrange  -  Set the boundaries of the sub-image to be displayed in mapplot.
mapcolor -  Select mapplot colormap type and transfer function.
```

```
mapfunc  -  Change the transfer function used in mapplot.
beamloc  -  Change when and where mapplot plots the clean beam ellipse.
```